




PatternMaker Version 7 User's Manual

© 2005 ... PatternMaker Software





PatternMaker Version 7

User's Manual

June 2005

PatternMaker Version 7

© 2005 ... PatternMaker Software

All rights reserved. No parts of this work may be reproduced in any form or by any means - graphic, electronic, or mechanical, including photocopying, recording, taping, or information storage and retrieval systems - without the written permission from PatternMaker Software, with the exception of quoting brief passages for the purpose of reviews.

Products that are referred to in this document may be either trademarks and/or registered trademarks of the respective owners. The publisher and the author make no claim to these trademarks.

While every precaution has been taken in the preparation of this document, the publisher and the author assume no responsibility for errors or omissions, or for damages resulting from the use of information contained in this document or from the use of programs and source code that may accompany it. In no event shall the publisher and the author be liable for any loss of profit or any other commercial damage caused or alleged to have been caused directly or indirectly by this document.

Revised: June 2005.

Authors

*Tamara Pickrell
Brian Pickrell
Jim Pickrell*

Contributors

*Eugenie Naber
Thea Botter*

Cover logo by

J.K. Smith Designs

PatternMaker Software

*PO Box 70306
Bellevue WA 98005
425-644-8161
www.patternmaker.com*

Special thanks to:


The wonderful members of PMUG and customers we've talked to at shows who gave suggestions for new features and generously gave their time to help with testing.

Note about manual contents:

This manual includes documentation of features offered in every version of PatternMaker, from the Basic Viewer through the Marker Studio.

Please note that you may not see exactly what these pictures show, and you may not have access to all the described features and commands.

Section



Introduction

1.1 Welcome to PatternMaker!

PatternMaker is a computer-aided design (CAD) program designed especially for clothing pattern design. PatternMaker makes it easy and fast to make clothing patterns, and lets you automatically resize your patterns. In short, PatternMaker lets you do everything you used to do with scissors, pencil, and paper, but much faster. This program has many features that are different from any other program, but you can learn to use it quickly with this manual.

All PatternMaker programs include:

- *Custom patterns* Sizes don't matter! Use PatternMaker's collections of pre-designed garments to create basic patterns from your own measurements. For pants, for example, you can tell PatternMaker your waist, hip, and leg length measurements, and the pattern will be mathematically drawn to fit *you*!
- *Printing* PatternMaker lets you print your patterns on any printer that is supported by Windows, including desktop printers, plotters, and print-to-fax programs.

Deluxe Editor adds:

- *Editing* Use the pre-designed patterns as a starting point for your own unique designs. Practice pattern alterations on a pattern that you know already fits you.
- *Measurement tables* Save your measurements in a file, so you don't have to type them in for every pattern. Save measurement tables for your family and friends, too!

Home Studio adds:

- *Drawing* Draw new patterns using the same procedures you use now to draw patterns on paper. Change, edit or save existing patterns.
- *Tools* Take advantage of advanced drawing tools such as facings, pleats, and darts.
- *Layers* Use layers to help organize objects in your drawing.
- *Macro Project Editor* Create your own simple macros to use with PatternMaker!
- *Customization* Set up PatternMaker to look and work the way you want.

Advanced Features:

PatternMaker Grading Studio and Marker Studio are for the professional pattern cutter or designer, and have many powerful features for the serious user. These include:

- *Digitizers* Use a digitizer tablet to "trace" patterns from paper originals or books. If the original was not full-scale, you can automatically expand it to life-size.
- *Grading* Grade your pattern according to your own grading rule. Make your own pattern in Size 10, for example, and PatternMaker can convert the pattern to sizes 8, 12, and 14. Save a grading rule simply, easily, and quickly, and apply that grading rule to any other pattern.
- *Special symbol libraries* These contain commonly-used symbols such as buttonholes, grainlines, arrows, etc., which you can insert into your pattern. One basic symbol library is provided with PatternMaker. In addition, if you have Grading or Marker Studio, creating your own libraries is as easy as saving a file.
- *Marker features* PatternMaker Marker Studio lets you arrange pattern pieces and print production markers. Special features let you pack the pieces together for maximum material efficiency, set cut ratios, and print reports showing material used and other information.

1.2 What's new in Version 7

We've incorporated many user ideas, and added a few neat things we thought up on our own:

- ***style option pictures in pre-designed garments***
see an illustration of each garment style choice
- ***measurement pictures in pre-designed garments***
see a descriptive illustration with written instructions for each measurement
- ***auto-arrange in pre-designed garments***
pattern pieces no longer overlap each other when the pattern is drawn
- ***dramatic new LaunchPad interface***
visual navigation simplifies finding, saving, and managing patterns; save a diagram and descriptive text along with a pattern file
- ***completely redesigned Print Preview***
interactive preview screen lets you click on specific pages to print
- ***new drawing and editing commands***
try the new "Right Angle," "Continue," and the great "Compass" feature; quickly divide a line segment into equal parts with "Divide Segment;" draw automatic pleats and dart caps
- ***multiple Undo/Redo***
keep an undo/redo history as long as you like, limited only by your computer's speed (longer undo history requires more processing power)
- ***mouse scrolling***
use the scroll wheel on your mouse to zoom in and out in your drawing
- ***expanded color options***
select your drawing color from any of the millions of colors available in Windows
- ***Yardage Grid improvements***
new "Toggle Yardage Grid" shortcut key; Yardage Grid can be included on Print To Single Page, for printing pattern layout diagrams
- ***Internet registration***
take care of registering your own program; easily re-register if you change computers
- ***extensive new "Configure" options***
add and arrange buttons on the icon bar; attach macros to a button; re-assign Hot Keys; save permanent configure options separately from temporary configurations; each user profile on the computer can have separate configurations
- ***new Lock Layer feature***
keep objects visible but "inaccessible"; useful when copying or tracing!
- ***new Save As Macro feature (Studio products only)***
create limited macros simply by drawing things in PatternMaker!
- ***added "Tip of the Day" feature***
helpful tips greet you each time you start the program

- **interface & usability improvements**
new "Start Panel" lets you select a task to begin; page alignment marks changed to circles; use quotes in text strings
- **improved Insert Symbol interface**
see a preview of symbols, objects, or groups contained in the current library file
- **several new grading features (Grading and Marker Studio only)**
simplified "Add Arrow" behavior; improved Read Table feature automatically matches named arrows with corresponding named points

1.3 Manual conventions

As you read through the User's Manual, or consult the Help file, you will notice that some words or phrases appear in different typefaces:

Keys to press on your keyboard

Represented by capital letters, enclosed in brackets:

example: <ESC>
means: Press this key

example: <CTRL>+<F3>
means: Press the first key and hold it while you press the second key, then release both

When the computer is telling you something

This font is used to represent the instructions that appear on the command line:

example: Rotate around what point?

Things to select from the menus

Menu items appear in quotes, and the name of the menu appears in bold type:

example: Click "Save" on the **File** menu

Mouse clicks

example: **LM** or **RM**
means: click the left mouse button or click the right mouse button

1.4 Time out for basics

WINDOWS BASICS

If you are brand new to computers, take some time to go over this section. Make sure you are familiar with the following terms, since they will be used frequently as you read through the manual and the tutorials.

Click

Move the mouse around until the point of the mouse cursor is pointing where the directions instruct you. Press the left button once and then release it. If the directions say "click," it always

means one click. If they mean two clicks, they will say "double-click." Also, when this manual simply says "click," it means with the left button. In PatternMaker, "right-clicking," has special functions.

Double-click

Move the mouse around until the point of the mouse cursor is pointing where the directions instruct you. Press and release the left button twice, quickly. Be careful not to move the mouse as you do this. If nothing seems to happen, try clicking faster, and be sure the mouse does not move.

Icons

These are small pictures that represent actions. They are shortcuts to commonly used program commands. Click once on an icon to execute its command.

Menu bar

The row of words across the top of the PatternMaker window. This is where you find all the commands of the program. When you click on one of the menu items, you get a "drop-down menu". These menus are associated with the menu item that they drop down from. For example, the menu that appears when you click the word "File" is called the **File** menu.

If you need more help with any of these, you can find full details in your Windows manual or Help section.

PATTERNMAKER BASICS

Object

Something that is drawn in PatternMaker. There are four types of objects, but the two types main types you'll be concerned with are Polygons and Text. A Polygon object is "a shape" -- circles, lines, octogons, sleeves, pockets, etc. A Text object is a descriptive label that you can add to any part of a drawing.

Vertex (vertices - pl.)

The beginning/end of a line segment, or the place where two line segments come together. For example, a triangle (a Polygon object!) has three vertices, one at each corner. Sometimes we'll also use the word *point* to mean *vertex*, simply because it's a more familiar word. (The menu that contains commands relating to vertices is even called the **Point** menu.) At other times, the word *point* may be used to mean *spot* or *location*, as in, "...the point where the two lines intersect." The meaning should be clear from the context.

Points vs. Objects

Points and objects are related, obviously, since objects are made up of points, but in PatternMaker you interact with them entirely separately. Commands that affect entire objects (ERASE, CUT, MOVE, etc) are found on the **Edit** menu; commands that affect individual points (MOVE VERTEX, DELETE VERTEX, etc.) are found on the **Point** menu.


1.5 Starting the program

When you install PatternMaker, it creates an icon on your desktop. This icon looks like a needle and thread:



Let's go! Double-click on the icon to launch the program.

Section



Learning the Basics

2.1 Program overview

Okay, you've got PatternMaker -- now what? Here's a strategy on getting started:

- Read through the "Program Overview" and "LaunchPad Interface" sections.
- Read the section on "Patterns and Printing." Have someone help you take your measurements (follow the directions [here](#)^[46]), and then try the sample pants or the fitting bodice to check that your measurements were taken properly (follow directions [here](#)^[46]).
- Read the rest of Section 2 ("Getting around in the program" and "Customizing PatternMaker"),
- Read the sections on drawing and editing. Don't get bogged down; if there's something you don't understand, it will probably make more sense after you've done the tutorials.
- Do the tutorials. Be sure to do them in order. Once you've learned something in a tutorial, feel free to use it.
- Read the remaining chapters of the manual while you are working through the Tutorials. Use the "Reference: Menu Commands" sections to look up any commands you don't understand.
- Make some patterns on your own. Remember, this is what you bought PatternMaker for! The fastest way to learn is by doing -- this is as true for PatternMaker as for anything else. You'll find that you don't need to know every single command before you can start getting to work.
- Read the rest of the manual systematically. Try every command at least once.

Use the manual, the tutorials, and the Help system together to help you learn PatternMaker. You can access context-sensitive Help by typing <?> at any time during a command.

The first sections of the manual explain the basic concepts. The "Reference" section gives the details of how each command works, and the tutorials guide you through the important features so you can see them in actual use.

Once you learn how to do a few commands, you can start using PatternMaker to make your own patterns. As you get comfortable with the program and develop your own techniques, keep referring back to the manual and you will keep learning new things. If you take an organized approach to learning this program, you will be making patterns in a short time!

Getting help

There are several avenues available to you if you need help.

1. First, check the Help file. It has been expanded to make it easier to find what you need. You can access the Help file from the **Help** menu, or by typing ? during a command to access the context-sensitive help.
2. Next, check the Index of the User's Manual, and the Index of the Tutorial. You may be able to find a reference to something you didn't notice in the Help file.
3. If it's a piece of terminology that's puzzling you, check the [Glossary](#)^[166].
4. Finally, you can contact technical support by phone or by e-mail. Also consider joining the PatternMaker User's Group e-mail discussion list. Check the PatternMaker web site for instructions on how to join:

www.patternmaker.com

You can use the link in the "About" box (located on the **Help** menu) to automatically launch

your browser and go directly to our site.

5. As long as you're there, check the web site for an answer to your question. We've posted answers to many frequently asked questions, and you may find what you need in that reference.

Folders and file organization

If you plan to use the LaunchPad interface, these file locations cannot be changed.

Program Files

By default, PatternMaker expects to find all necessary files in the "C:\Program Files\PatternMaker Software\PatternMaker 7" folder. If you prefer to install the program to a different folder or on a different drive, specify the proper location when the Setup program asks you for it.

User Files

When you open the program for the first time, a special folder is created. This is located at "My Documents\PatternMaker\Personal Files." Under this folder are three subfolders, for personal measurement tables, grading tables, and saved patterns.

If your computer has more than one user profile, each profile will have its own user file location.

Shared Files

Files such as the garment collections, master measurement templates, and library files are shared among all users. A folder for each designer is created under "PatternMaker 7\Common Files\Designers," and each garment collection is installed in a subfolder under its designer. You can also choose to save pattern files and grading tables in the shared location. These files are located under the "PatternMaker 7\Common Files" folder.

See also:

[Show shared files](#)  ⁹⁶

[LaunchPad vs Windows dialogs](#)  ⁹⁴

Measurement units

One of the first decisions you'll make when you start PatternMaker is whether you want to work in inches or centimeters. (Depending on which version of PM you're using, it may have asked you this question during setup.)

Your choice of measurement units will affect the following things:

- pre-designed garments: the garments will check to see which units you selected, and the default measurements will be displayed to you in that format. You will enter your own measurements in that format.
- seam allowances: enter your desired seam allowance using your chosen measurements
- grid: the default size for the alignment grid is one "unit" -- either 1 inch or 1cm.
- text: determines the height of text -- a text height of "2" is either 2 inches or 2 cm


- Dim: determines the size of the number labels on Dim objects

What's on the screen

Start Form



The new Start form helps you easily select how you want to use PatternMaker when you open the program.



- Use a pre-designed garment (macro): Select a pattern (.MAC file) from a garment collection you have installed (see [Open a pre-designed garment](#)^[201])
- Open to a blank drawing area: Begin drawing something from scratch
- Open a saved pattern: Open a pattern you've created from scratch, or saved from a macro
- Read the "What's New" help topic: Find out about all the new features of Version 7
- Read the "Getting Started" help topic: Gives you some basic step-by-step instructions on using the Ladies' pants macro. It takes you through the steps of [creating a measurement table](#)^[144], starting the macro, selecting garment options, and printing the pattern.
- Exit: Closes PatternMaker

If you check the "Do this by default" box, the program will always perform the selected option without displaying the form. If the form has been turned off in this way, you can turn it back on by selecting the option on the "Configure" or "Configure Defaults" form found on the **Settings** menu.

See also:

[Tip of the Day](#)^[14]
[Types of files](#)^[102]

Tip of the Day




The Tip of the Day introduces you to new features of Version 7, and may help you become familiar with other ways of doing things that you never thought of before.

The Tip of the Day box appears immediately after the Start Form, before you access the drawing area. If you don't want to see the Tip of the Day, clear the checkbox on the Start form.

Parts of the screen

When you start PatternMaker, what you see is the main drawing screen. The standard Windows components -- the mouse, the drop-down menus, and the dialog boxes that appear from time to time -- work the same way they do with any other Windows programs.

Let's stop and see what we're looking at:



The **drawing area** contains all the objects in your pattern, whether you draw them yourself or use one of the pre-designed garments. You can think of the drawing area as the viewfinder on a camera; it shows a limited section of an area that stretches out in all directions. You can zoom out, zoom in, or pan to different areas of the drawing using the arrow and page up/page down keys. We'll get to those commands in a few minutes.

Three grids are available to you as you work:

- alignment grid (dots), to help in positioning objects. See [Measurement Units](#)^[12]
- page grid (blue dashed line), to show how pattern pieces will be printed. See [Page Grid](#)^[55]
- yardage grid (red dashed line), to help you estimate fabric usage and create a pattern layout. See [Yardage Grid](#)^[52]

The drawing area is white by default, but it can be changed to black if you prefer. See [Custom Settings: Screen Color](#)^[79] for details.

The **command line** (or **prompt line**) is where PatternMaker gives you messages and asks you questions. The most recent prompt appears at the bottom. **It is very important to read these prompts.** If the computer does something that you don't expect, it's usually because the command you think you're running is not the command the program thinks you're running. Reading the prompt line and the status bar will let you know what the program is trying to do.

Most inputs you type into the program (such as coordinates) will also appear on the command line. (However, for certain commands your inputs will go into a dialog box instead.)

When the computer is ready for you to choose a new command – a drawing tool, editing function, etc. – it will display the command prompt, which looks like this:

Command :

If you don't see this, it means you are still in the middle of another command.

The **menu bar** is where you select a command. These menus work just like menus in any other Windows program, with shortcut keys and some sub-menus.

The **icon bar** provides shortcuts to some frequently-used commands. The icons will change depending on what step of a command you are in. (For example, icons for editing commands do not appear if you do not have any objects on the screen to edit.) Right-click on a button to get help about that command.

The **status bar** gives you information about the current drawing conditions -- drawing color, layer, line style, mouse coordinates, etc -- as well as the current (or most recent) command.

List of Icons

This is the arrangement of icons when you install PatternMaker. Most commands have an icon available, as you can see pictured on the menus, but not all of them are set to be visible by default.

You can change the visible icons on the *Icon Bar* tab of the Configure form (found on the **Settings** menu).


When you open the program:



When you have a drawing on the screen:



The Edit Commands:




See also:

[Configure: Icon Bar](#) [152]

Alignment grid

The alignment grid can help you position points and objects, and gives you an idea of an object's size. The default spacing of the grid is one "unit" (either one inch or one centimeter, depending on your settings), but you can change the grid spacing to anything you want.




You can turn this grid off and on with the <F4> shortcut key, and you can change your Configuration settings to determine whether the grid is on or off by default when you open the program.

See also:

[TOGGLE GRID command](#) ¹³⁵

Showing/hiding points

Every object you draw is made up of points. A point is placed automatically where a line segment begins, ends, changes direction, or curves. Editing a pattern, or drawing one of your own, is accomplished by moving points around or adding new ones. In order to move points or perform other actions, you often need to see exactly where the points are in your drawing, since they do not necessarily fall on a line.



Line points appear in **blue/cyan**, and corner control points appear in **green**.

You can turn the points off and on with the <F5> shortcut key, and you can change your Configuration settings to determine whether the points are turned on or off by default when you open the program.


See also:

[SHOW VERTEX command](#) ¹³⁶

2.2 LaunchPad Interface

With Version 7, PatternMaker introduces a dramatic new file interface called LaunchPad.

LaunchPad makes it easy to find and use your patterns and saved files, without worrying about "losing them" somewhere on your computer. The designers and garment collections are represented by folders. Each garment collection and the individual patterns have illustrations, to help you choose a project. And, style options within each pattern are now illustrated as well!



Each of the pre-designed garments comes with a descriptive summary, and you can also write a comment about patterns you save, to help you identify them later.


Read more...

[Finding and opening a pattern](#) ²⁰

[Saving a pattern](#) ²¹


The LaunchPad interface is active by default, but if you're an old hand at PatternMaker, and

want to work with the original file interface, that option is still available! Select "Configure Defaults" from the **Configure** menu, and then click the "Advanced..." button. Look in the column of options to the right side of the form, and put a mark in the "Use Windows Browsers" checkbox.



Select a designer

The LaunchPad opens to the Designer's list. A folder represents each designer whose collection(s) you have installed.



Double-click on the designer you want, or click once and then click the "Open" button.


Next: [Select a garment collection](#)²⁰

See also:

[LaunchPad view options](#)²²

Select a garment collection

Each garment collection is represented by a folder. Click once on a folder to see the description and focus picture. Open the folder to see the individual garments in the collection.



Next: [Open a file](#) ²⁰


See also:

[LaunchPad view options](#) ²²


Open a file

The LaunchPad helps you find patterns from the garment collections as well as saved patterns that you've made.

Each garment in a collection has a description and a focus picture to help you select the one you want.



Saved pattern files have a standardized focus picture, and display any comments you wrote when you saved the file.



Select the file you want, then click the "Open" button.

See also:


[LaunchPad view options](#)^[22]

[Folders and file organization](#)^[12]

[OPEN command](#)^[106]

Save a file

When you want to save a pattern file, you'll use the LaunchPad "Save" window. It is very similar to the other LaunchPad windows: space for a file name and description, a focus picture, and the list of files and folders.



If you're really feeling adventurous, you can create your own focus picture to go along with your new file. The requirements are:

- the image must be in .jpg format. This could be a line drawing, or even a photo of the finished garment.
- maximum dimensions are 250x250 pixels
- the image must have exactly the same name as the pattern, other than the .jpg file extension
- it must be located in the same folder as the .pat file

See also:


[LaunchPad view options](#)^[22]

[Folders and file organization](#)^[12]

[SAVE command](#)^[107]

LaunchPad view options

The LaunchPad give you a lot of flexibility in how you locate and view your files. In the file area, you can choose between different icon sizes, much like the options in the standard Windows Explorer.




Large icons:




List:



You can also choose to view the Windows Explorer tree, or keep it hidden in the "simple" view. With the Explorer tree visible, files can be located in places other than the default folder.



With the tree hidden, your files can always be found in one place, and you have a larger window available for viewing files and folders.



2.3 Getting around in the program

Interacting with the program

It is possible to select, customize, and print a pre-designed garment with little more than a dozen mouse clicks. But you want to do more with PatternMaker, right?

To do so, you need to become familiar with the viewing, editing and drawing commands. You will learn:

- how to change your view of what's on the screen
- how to use the mouse in PatternMaker
- different ways to activate a command
- steps in using commands
- how to use X and Y coordinates

See:

[Looking around: PAN and ZOOM](#) ^[24]

[Using the mouse](#) ^[25]

[Different ways to select a command](#) ^[26]

[Hot Key functions](#) ^[28]

[Selecting objects and points](#) ^[30]

[X and Y coordinates](#) ^[34]

Looking around: PAN and ZOOM commands

There are several tools you can use to view different parts of your drawing. ZOOM changes the scale of the drawing, appearing to move you closer or further away. PAN moves you up, down, right, or left.

Remember that your drawing doesn't change when you zoom or pan; only your view of it changes. Think of the drawing area of the screen as the viewfinder on a camera that moves around to get different views of the drawing.

All the various ZOOM and PAN commands can be selected either with icons or from the "Zoom" submenu on the **View** menu. Most can also be selected with [Hot Keys](#) ^[28].

Special Zoom and Pan Keys

PatternMaker provides some special short cut keys to make it easier to activate the most commonly-used ZOOM and PAN modes:

<PgUp>	Zoom Out
<PgDown>	Zoom In
<End>	Zoom All
arrow keys	Pan (Left, Right, Up, Down)

ZOOM with the mouse scroll wheel



If you point your mouse into the blue command line area, or a blank part of the icon bar, you can zoom in and out with your mouse scroll wheel.

Using the mouse

Understanding the function of the mouse buttons is one of the most important things necessary for success with PatternMaker. The mouse clicks activate, advance, and conclude all the commands you will use.

The **left mouse button** is used for selecting things. Use it to select:

- menu commands
- icons
- points
- objects

Many commands let you select more than one object or point at once. For example, the MOVE command will move one object or every object in the drawing.

Some commands let you select only one object at a time. With the OFFSET command, for example, you can add a seam allowance to one object at a time.

We will use the abbreviation **LM** to indicate a left mouse click.

The **right mouse button** is used to confirm what you have selected.

It indicates to the program that you have finished selecting things and are ready to proceed to the next element of the command.

We will use the abbreviation **RM** to indicate a right mouse click.

The <ESC> key can be used interchangeably with **RM**.


The basic rules of mouse operation are:

- If you're drawing something, use **LM** to enter a point.
- If you aren't drawing something, use **LM** to choose a command or answer a question.
- Use **RM** to end whatever you're doing.
- Don't "click and drag" like you do with many other computer applications. Just click the button and let it up.

II: Learning the Basics

- The normal mouse cursor looks like an arrow. An hourglass-shaped cursor means you should wait for the computer to finish what it is doing.
- If the mouse cursor is outside the PatternMaker window on your computer screen, your inputs won't be read by PatternMaker.

The Mouse Coordinates box in the menu bar will tell you the current position of the mouse.



These are standard X-Y coordinates. The first number is the X, or horizontal, position and the second number is the Y, or vertical, position. (See [X and Y Coordinates](#)³⁴ for full details.) These numbers represent either inches or centimeters, depending on the measurement units you chose during program setup. You can also change the units at any time, by simply clicking on the Mouse Coordinates box in the menu bar.

Different ways to select a command

There are several ways to select a command with PatternMaker: icons, menus, drop-down boxes, typed commands, and Hot Keys. Most commands are accessible in more than one way. Use whichever is most convenient at the moment.

When you have selected a command, the command's name appears in green in the Status Bar. When you finish the command, its name turns purple.

Icons

Standard Icons

The icons are provided to make it easy and quick for you to use PatternMaker with a mouse. If you learn how to use the icons, they will make your work faster and easier. However, you never have to use the icons at all – everything that you can do with icons can also be done with either a menu choice or a typed input. Use whichever is most convenient for you.

You can activate a command by clicking an icon with the left mouse button (**LM**). Clicking the right mouse button (**RM**) on an icon will give you the Help information for that icon.

Context Icons

As soon as you start a command, a different set of icons will appear in the icon area. These icons represent options that you can select while doing a command. The icons that appear will vary, depending on the command you selected, and on what choices are available.

Example: When you first start PatternMaker, there is nothing in your drawing, and the MOVE icon doesn't appear. This is because there is nothing to move. After you draw an object, the MOVE icon and several others appear.

Example: When you select the MOVE command, a different set of icons appears. These are the Selection icons (see below). These are options you can use while selecting objects to move.

Remember that not all commands are represented by icons – if you don't see an icon for a command, you may still be able to select it from a drop-down menu.

Menus

You can select the drop-down menus at the top of the screen with the mouse. When the menu

appears, click the mouse on the command you want. This works like any other Windows application.

A menu item with an arrow next to it (➤) leads to a submenu with more choices.

If a menu item is not available, it will be grayed-out and you cannot select it. For instance, you can't select the MOVE command if there aren't any objects for you to move.

Selecting menus from the keyboard:

Select a drop-down menu by holding down the <ALT> key and typing the underlined letter in the menu's name. When the menu appears, use the up and down arrow keys to highlight the menu item and press the <ENTER> key. Or type the key letter of the item you want. The key letter for each menu item is underlined. (Most Windows applications work the same way.)

Example: Press <ALT>+F to select the File menu

Drop-Down Boxes

Many configuration commands can be selected from the drop-down boxes on the Status Bar. These include the current drawing color, current line color, style, and width, current Snap mode, and more. Any changes you make will remain in effect until you change them again.

Typed Commands

You can select any command by simply typing the name of the command. The letters you have typed will appear on the prompt line at the bottom of the drawing area. Press the <ENTER> key and the command will start. The chapters on Menu Commands give full lists of the commands available for PatternMaker.

Sometimes the proper name of a command is slightly different than the name listed in the menu. To find the proper name of a command, look for the command's name in the menu bar after you select it.

Hot Keys

The function keys <F1> through <F12> and various other special keys on your keyboard can be used to run certain commands. These are called the "hot keys." The [Hot Key commands](#)^[28] can be selected at any time, even if you are in the middle of another command. For instance, while doing the MOVE command, you may zoom in to see a very small object you want to select, then zoom out until the destination comes into view.

(Most of the Hot Key commands can also be selected with icons. These icons appear after you select a command.)

You will find that using the Hot Keys is essential to using PatternMaker. Tutorial 2 gives you an introduction to how they work.

See also:

[Configuring Hot Keys](#)^[153]
[Configuring the icon bar](#)^[152]

Hot Key Functions

The hot key functions are special functions that can be selected by typing one of the Function keys (F1, F2, etc.) or other special keys on your keyboard. Some of these are also available through command lists or icons; others are options of other functions.

Hot key functions are useful because you can use any of the hot key functions even while doing another function.

You can reconfigure these key assignments if you want to (see [Configure options](#)⁸²), but these are the default settings:

FUNCTION KEY	FUNCTION
<F1>	Zoom out (makes everything appear smaller)
<F2>	Zoom in on the center of the drawing area (makes everything appear bigger)
<F3>	Zoom in on the mouse. To examine a detail of your drawing, put the mouse on it and hit <F3> a few times.
<F4>	Grid on/off. Shows or hides the grid points.
<F5>	Points on/off. Shows or hides the vertices of all objects.
<F6>	Select snap. A menu will appear, listing all available snap modes.
<F7>	Arrows. Shows or hides the grading arrows. This function toggles between three options: no arrows, arrows only, and arrows and their names.
<F8>	Absolute mode/mouse mode. Switches digitizer mouse modes. This only applies if you are using a digitizer.
<F9>	Pan to mouse. The view is moved so the current mouse location is at the center of the drawing area.
<F11>	Layers. Open the Layers dialog box.
<F12>	Page Grid on/off. Shows or hides the page grid.

For the following, hold down the <CTRL> key while typing the given Function key

<CTRL> F1	Snap off
<CTRL> F2	Snap to grid. Also shows the grid, if it's turned off.
<CTRL> F3	Snap to end point
<CTRL> F4	Snap to nearest
<CTRL> F5	Snap to ortho
<CTRL> F6	Snap to mid point
<CTRL> F7	Snap to intersection
<CTRL> F8	Snap to offset
<CTRL> F9	Snap to distance from end point
<CTRL> F12	Yardage Grid on/off

See also: [Using Snap Modes](#)³²

Other hot keys:

<Pg Up>	Zoom out
<Pg Down>	Zoom in
<Home>	Zoom in on mouse
<End>	Zoom All. Shows all objects.
<Arrow keys>	Pan up, down, left, right

See also: [Looking around: PAN and ZOOM](#)^[24]

Activating a command

After you activate a command, you will usually be asked to select the object(s) on which the action will be performed. This is done by left-clicking on one or more objects. Every command has at least two steps that you must either complete or cancel before you can do anything else. Some commands that ask you to select things have more than two steps. If you are in the middle of a command, this is indicated by the command name in **green** at the far right side of the status bar.



Then you must let the program know you are done selecting by right-clicking the mouse, or by pressing the <ESC> key. The command will then complete its action or, in some cases, request additional information from you. (See the Reference section for step-by-step instructions for each command.)

When you have finished a command, the command name appears in **purple/italics** in the status bar. You must complete the current command (or cancel it) before you can begin a new command. To cancel a command, click the **RM** button, or press the <ESC> key.



The most recent command you have used remains "available" until you select a different command. This is a convenient way to repeat a command without having to continually select it from the menu or click the icon. For example, if you have just drawn a rectangle, you can immediately draw a second rectangle simply by beginning to click its first point.

If you find yourself in a situation where the commands you want are not available and it seems that you can't do anything, check the status bar. You probably have a command listed there in **green**. Green means you're in the middle of a command, and the program is waiting for further instructions from you. You have two options at this point:

- If you didn't mean to be in the middle of a command, right-click your mouse or press <ESC> until the command name turns **purple**. (This may require more than one click/press.) When the command is purple it means it is inactive, and you can continue with some other action.
- If you are in the middle of a command and don't know what to do next, check the command line. It will give you instructions on what it is waiting for.

See also: [Selecting Objects or Points](#)^[30]

Repeating a command

If you click the mouse on the screen again after you've finished a command, the last editing or drawing command you performed will be repeated. This allows you to draw or edit many objects without having to select the same command icon over and over. If you aren't sure which command will be repeated, the command's name is displayed in purple on the far right end of the status bar.

Be careful about clicking the mouse in the drawing area indiscriminately – it's easy to repeat a command without meaning to.

Remember: if you don't understand what the computer's trying to do, read the prompt line.

Canceling a command

To cancel a command, click the **RM** button, or press the <ESC> key. Some commands have more than one step, and therefore require more than one click.

Remember, you haven't cancelled the command until the command name in the status bar turns back to purple italics!

Multiple Undo/Redo

If you complete a command and realize it wasn't what you wanted, you can undo the change with the UNDO command.

With Version 7, you can now take advantage of the multiple undo/redo feature. The program configuration determines how many steps you can undo. More undo steps require more computer memory and will make the program run more slowly, so you can adjust the undo number to something that you like. The default is 9.

See also:

[UNDO command](#)¹¹⁷
[REDO command](#)¹¹⁸

Selecting objects and points

Selecting objects or points is the second step in any editing function, after you have activated a command. Most commands require you to select one or more objects, or one or more points, on which to perform an action. Here is the basic procedure:

- Use **LM** to click once on each thing you want to select.
- If you're selecting points, try using Snap To Endpoint (<CTRL>+<F3>). The mouse cursor will jump precisely to the nearest vertex. You can also use the [ZOOM commands](#)¹³⁷ to focus closely on the area you want to view.
- If you're selecting objects, click near the edge, not in the center of the object.
- An object will get highlighted when it is selected. A vertex (a point) will turn red when it is selected.
- Use **RM** to indicate that you've finished selecting things. The command will then continue to the next step.

Some editing commands only work on one item at a time. In this case, if you select a second object or point, the first is unselected. Other commands, such as CUT and JOIN, require you to select two objects, one at a time. The rest of the commands can work on any number of objects.

Note: You cannot select a mixture of objects and individual points. For commands on the **Edit** menu you select entire objects; for commands on the **Point** menu you select individual points.

There are three ways to select objects or points:

[one-by-one](#)³¹ [selection window](#)³¹ [select all](#)³¹

Selecting one-by-one

- Click on the object or the point: **LM, LM, LM...** until each object/point you wish to select is highlighted.
- Accept the selection set -- **RM**

Selection window

- Type <w> or click the Selection Window icon
 - Indicate one corner of the selection area -- **LM**
 - Move the mouse diagonally and indicate the opposite corner of the selection area -- **LM**
- Any object that has a point within this window will be selected (highlighted).
Window selection never un-selects objects.
- Accept the selection set -- **RM**

Note: you can use the selection window in combination with the method above, before ending the selection set.

Selecting all objects

- Click the All Objects icon, or type <A>
Every visible point (and therefore every visible object) in the drawing will be highlighted (selected).
Note: objects are not selected if they are on a layer that is locked or turned off.
- Accept the selection set -- **RM**
Note: you can use "All Objects" in combination with either or both of the methods above, before ending the selection set.

Unselecting

If you accidentally select something by mistake, just click on it again (**LM**) to un-select it. An object will be "un-highlighted" (its original appearance) when you unselect it; a point will return to its original color (not red).

Using Snap modes

One of the most helpful -- and most under-used -- features of PatternMaker is the many Snap modes.

A Snap mode makes the cursor jump to a precise location, so you don't have to worry about being so precise as you move the mouse around. When you are "in" a Snap mode and you enter a point with the mouse, the "snap point" closest to the mouse location is entered, rather than where the mouse cursor is actually pointing. This makes it possible to enter a point with 100% accuracy.

You will often need to switch between snap modes while you are in the middle of some other command. Therefore, all of the Snap modes can be selected with icons and Hot Keys.

Example:

Move a skirt piece so that its center back point is aligned with the grid

1. Activate the MOVE command.
2. Select object to move: **LM** on skirt piece; **RM** to finish selecting
3. Turn on Snap to Endpoint: <CTRL>+<F3>. Cursor jumps to nearest vertex.
4. Select base point for move: **LM** on center back point
5. Turn on Snap to Grid: <CTRL>+<F4>. Cursor jumps to grid points.
6. Select destination for move: **LM** on a grid point
7. MOVE command is finished.

Here are the most common Snap modes:

Name: Snap Off
Hot Key: <CTRL>+<F1>
What It Does: Turns off any active Snap.
Why You Would Use It: When you want the cursor to move around normally.

Name: Snap to Grid
Hot Key: <CTRL>+<F2>
What It Does: The cursor jumps from one grid dot to another. (And you can customize the size of the grid.)
Why You Would Use It: Align the edges of objects; quickly move something a distance equal to the size of the grid.

Name: Snap to Endpoint
Hot Key: <CTRL>+<F3>
What It Does: The cursor jumps from one point in an object (a vertex) to another.
Why You Would Use It: Essential for moving individual points; excellent for selecting a rotation point.

The other Snap modes are discussed in [Advanced Topics](#)¹⁰³.

Special selection tips

- If it's hard to tell what you're selecting, try using the Show Vertices command (<F5>) to show the vertices, and/or zoom in (<F3>) to get a better view.
- For polygon objects, click **LM** on one of its points or anywhere on the edge (not the inside) of the object.
- Note that the Xarc points (corner control points) are not actually on the polygon; they are near it.

- Clicking on a vertex always selects the entire object. (Try using the [Snap To Endpoint snap mode](#)^[32].)
- You can't select an object that is on a locked layer (see [Layer Lock](#)^[102]).
- For some functions, PatternMaker doesn't just want you to select a point, but the line segment or arc connecting two points. Just put the mouse on the appropriate segment and click.
- For text objects, click on the lower left corner.
- For symbol objects, click on the insertion point.
- For dimension objects, click on either endpoint.
- Click **RM** or press the <ESC> key when you are done selecting objects.

Often if several points or objects are close together you will have difficulty selecting the one you want. There are several ways to deal with this.

- If points from two objects are placed at the same location, the X marks cancel each other out, and will not be visible. Put one or more of the objects on a different layer and turn the layer off. (See [Using Layers](#)^[98]). This will get them out of the view and make your work easier.
- The ID Object Panel can also be very useful in cases where you are having trouble figuring out why a point is not getting selected. Sometimes an object will have several points in the same position, or you may find that two different objects have points in the same place. The ID Object Panel will help you sort this out.
- Read about the **NEW** [point selection window](#)^[33].

If you can't find an object that you know is somewhere in the drawing, check these things:


- Objects out of view in the drawing area: The easiest solution here is to select "Zoom All" from the menu. You can also use the Function keys or icons to zoom/pan to where the object is (See ZOOM and PAN functions).
- Layer off: If an object isn't showing because it's in a layer that's turned off, there is no way to select it. Use the LAYERS command to turn on all the layers you need before selecting a command. For more information about how to turn layers on and off, see [Using Layers](#)^[98].

Using the point selection window



Sometimes when you need to select a point, you find that more than one object has a vertex at the same place. If the object you want is underneath another, it can be difficult or impossible to select the correct point. You can get around this problem by switching layers, or using TO FRONT and TO BACK, but an easier way is the new point selection window.

If you click a point at a location where two objects overlap, a point selection window opens, with a list of the objects involved. If the objects have names (NAME OBJECT), the names will be listed; otherwise, all objects will be listed as "No Name." When you select an object from the list, the corresponding object on the screen is highlighted. In this way, you can select the object containing the point you want, even if you can't tell which object it is in the list.



See also:

[Special selection tips](#) ³²

X and Y coordinates


As you move around in the whole vast drawing area, which spreads out infinitely in all directions, you need some way to keep track of where you are. You also need a way to supply input to PatternMaker as you are drawing your pattern. PatternMaker uses a grid system of **X,Y** coordinates, somewhat like the *N, S, E, W* designations of street addresses.

If it's been a while since that high school math class, here's a quick refresher course:


Imagine one horizontal line and one vertical line coming together in an intersection. The point where they cross is called the origin. This is the "zero" point.

Every position on the screen can be represented by a pair of numbers. The first number in each pair represents the distance from the origin in the **X**, or horizontal, direction. The second number represents the distance from the origin in the **Y**, or vertical, direction. The origin is given the coordinates 0, 0.

The horizontal line to the right of "zero" is the positive X direction; to the left is the negative X direction. The vertical line above "zero" is the positive Y direction, and below is the negative Y direction (see diagram). The lines extend infinitely in all four directions.



In PatternMaker, the status bar tells you the position of the mouse cursor at all times (see illustration below).



To find the position of a point, simply count the number of units (either inches or cm, depending on your program configuration) to the right or left, and then count the number of units up or down. That pair of numbers is the *coordinate position*.


At any given moment, your view of the drawing area is limited to the boundaries of your screen. The origin ("zero point") may be far off the screen, but the position indicator helps you keep track of where you are.

As mentioned above, coordinates are used not only for PatternMaker to tell *you* something (where you are in the drawing), but also for you to tell PatternMaker something -- where you want to put something. There are four types of coordinates that you can use: [absolute](#)^[35], [relative](#)^[36], [polar](#)^[36], and [relative polar](#)^[36].

Absolute coordinates

Somewhere in the drawing area is the "0,0" point -- the place where the horizontal measuring line meets the vertical measuring line.. In reality, you probably won't pay attention to where this is. You'll be busy zooming and panning around and won't ever notice where "0,0" is. But it is important to realize that it exists, because it explains the numbers in the mouse coordinates area on the status bar.

Absolute coordinates are always measured from the point 0,0 -- the origin of the grid. For example, point (2, 1) is two units to the right of the origin, and one unit above the origin.




Relative coordinates

Much more relevant to your regular work is the idea of "relative" coordinates. This simply means that you are measuring from your last point, rather than from that elusive "0,0" location.

Scenario:


You've experimented with zooming and panning and you have no idea where you are on the screen. Now you want to draw a 3x5" rectangle. You could draw from 0,0 to 3,5, but who knows where that "0,0" point is by this time?

The "@" sign is used to indicate that the next coordinates you type are going to be of the relative type. For example, Point A is at position (1,1); if you enter @2, 1 for the following point, it is positioned two units to the right of, and one unit above Point A. Its absolute coordinates are (3,2), but you don't have to know that in order to draw the line.



Polar coordinates

Polar coordinates are a bit different from standard X,Y coordinates. Polar coordinates measure distance and degrees, rather than distance and distance. Polar coordinates appear as two numbers separated by an angle sign < rather than a comma. The first number is the distance and the second number is the angle in degrees. Angles are measured from a base line that starts at the origin (0,0) and extends to the right. Positive angles go up and negative angles go down. For example, the position represented by 3<30 is located three units from the origin, at an angle of 30 degrees (diagonally upward).



You can also make polar coordinates relative to the last point you entered by preceeding the pair of numbers with the @ sign, as in [relative coordinates](#)^[36], above.

Example: Using coordinates in practice

When you are entering coordinates, you don't have to tell the program which type you are going to use. Just pick one and start typing -- PatternMaker will figure it out as you go.

Exercise 1: Draw a horizontal line 6" long

- Activate the LINE command
- Click **LM** anywhere in the drawing area, to indicate one end of the line
- Type @6, 0 and press <ENTER> (typing a space after the comma is optional)

Exercise 2: Draw a vertical line 4" downward from the origin

- Activate the LINE command
- Type 0, 0 and press <ENTER>
- Type 0, -4 and press <ENTER>

If you can't see your line after you do this, use the <END> key to Zoom All

Exercise 3: Draw a line 5" to the left and 2" upward

- Activate the LINE command
- Click **LM** anywhere in the drawing area, to indicate one end of the line
- Type @5, 2 and press <ENTER>

Exercise 4: Draw a line 7.5" long at a 45° angle

- Activate the LINE command

- Click **LM** anywhere in the drawing area, to indicate one end of the line
- Type @7.5<45 and press <ENTER> (typing a space after the < is optional)


Exercise 5: Draw a 10x4 rectangle around the origin.

- Activate the RECT command
- Type -2, -5 and press <ENTER> (absolute coordinates)
- Type @10, 4 and press <ENTER> (relative coordinates)

The origin (0, 0) should be located in the center of your rectangle.

Tutorial 3 gives more practice in using the various kinds of typed point inputs.

Section



Patterns and Printing

3.1 Using the pre-designed garments

Here's where we get into really using PatternMaker. In this section we will:

- talk about what "macros" are
- talk about how to take proper measurements
- use your measurements to create a personal measurement table
- use that measurement table to create a custom-fit test bodice
- print out the pattern and talk about putting it together

Your Custom Fit

What Are Macros?

Each PatternMaker macro is a small computer program which is run by PatternMaker. You will be asked to make some garment style choices and enter your measurements. The program then does some calculations and draws a garment pattern. The calculations are the same sort of calculations and measurements a pattern makers uses to draft a pattern with pencil and paper and ruler. The resulting pattern is made up of polygon objects which can be modified like any other object in your drawing. In other words, once you've made a pattern from a macro, you can do anything you like with the results.

One collection of women's garments comes with your PatternMaker program. Many other collections are available separately.

Why Use A Macro?

Ever been frustrated with patterns that do not fit? Do you buy patterns that fit your hips, but not your body? Don't you wish you could redraft your patterns to fit YOUR measurements, instead of having to use the sizes supplied by a pattern publisher? Do you feel overwhelmed by the thought of drafting a pattern from scratch, or just want a place to start? Macros could be the answer!

PatternMaker's system of macros create custom-fit sewing patterns from your personal measurements. These are more than just slopers – most of the macros draft complete patterns, ready to cut out and sew. You can create an entire wardrobe from a single set of measurements. You don't have to know anything about flat pattern drafting to get a good fit – although if you do, you may enjoy using the macros as a starting point for your own designs.

The macro system also offers unmatched flexibility and expansion opportunities. Many different designers can write macros that will work with PatternMaker. You're not limited to just the garments that come with the system.

Will It Really Fit Me?

The PatternMaker macros have been well-tested in real life. They are based on a fitting system that has been in use by custom tailors, working with pencil and paper, for years. The collection of macros included with this package have been written by professional tailor Leena Lähteenmäki, and all of the patterns have been tested on subjects with a variety of body types and sizes. We have found that they will fit nearly everybody, large and small. More important, the measurements are easy to take and the measuring instructions are easy to follow. If you do need to make adjustments, it's much easier to start with a pattern that already matches your measurements. If you make a mistake, or want to make a change, it's a matter of seconds to redraw a macro with different measurements.

Yes, But Will It Really Fit Me?

Our macro patterns will fit nearly everybody over a wide range of sizes and builds, but no computer-generated pattern will fit everybody. If you have a special fitting problem, such as an asymmetrical body, you may need to make adjustments on your own. The macros will give you a good starting point to work from.

Most of these garments require an intermediate or advanced level of sewing skill. If you do not already know how to assemble a garment, install a zipper, etc., you will need to refer to a general sewing text as well as the macro instructions and this manual. Please do not rush. We can give you the patterns, but it's up to you to sew the best clothes you can. For beginners, the Skirt macro is the easiest to make. For advanced sewists and pattern designers, the Bodice macro serves as a sloper, or fitting shell, to design your own patterns.

What Else Is There?

The Deluxe and Home Versions of PatternMaker includes the Women's Vol. 1 Garment Collection. The Expert and Marker Versions include three collections of your choice. Many other collections are offered separately. To find out what's currently available, check our web site at:

www.patternmaker.com

Where Do I Start?

To start making your own patterns, first have someone help you take your measurements. Your macro package includes a measuring chart which details all the measurements necessary for that particular collection. Make sure you're using the measuring chart specifically for the macro pattern you want to make. Different designers may use different drafting systems, and require different measurements, or that the measurements be taken in a slightly different way.

Note: Find someone to help you measure. Do not try to measure yourself. It will distort the measurements and give you poor results.

Next, save your measurements in a new measurement table (see [Using Measurement Tables](#)⁴⁵, below).

Finally, run the MACRO command and select the macro file you want to use. Each macro will be a bit different but they all follow the same general format:

- select garment options and answer questions
- select a measurement table (or enter measurements manually)


After you input the information for the macro, you will see an hourglass icon while the program runs the macro and draws the pattern. When the macro finishes, the hourglass will turn back to the pointer icon.

If you do not see your pattern, or if you see only part of it, press the <END> key on your keyboard to view the complete pattern.


What is a macro?

A "macro" is the technical term for the pre-designed garments. It is simply an automated sequence of commands which automatically perform the same steps you would use to draw a pattern from scratch. To create a pattern, the POLY command is run repeatedly (draws shapes), pausing at times to ask for your input (style selections and measurements); some text is added, button and grain lines are drawn, etc. (pattern details). And in the end, a custom-fit pattern is drawn on the screen.

The designer who creates the macro can make it very simple...



...or very complicated:



With PatternMaker, the pre-designed garments are a "modular" feature. You don't have to be limited to one person's (or even one company's) idea of what a "popular" pattern is. There are many creative people around the world who are developing all kinds of macros that can be used with PatternMaker.

It's important to understand that the options available in each macro depend entirely on the whims of the designer. Some macros will have style pictures; some may not. Some have an option to add seam allowance; some do not. Some are for sale; others may be given away at no cost.

Frequently Asked Questions:  165

Where do the macros come from?
Can I create my own macros?
Can I adjust the body measurements after a pattern is on the screen?

How to run a macro


These are the basic steps:


1. Click the "Macro" icon, or select "Macro" from the **File** menu.
2. Select a designer.
3. Select a garment collection, if the selected designer has more than one collection.
4. Select a pre-designed garment ("macro").
5. Follow the options in the macro: choose style options, if available, and enter your measurements.
6. Your pattern is drawn on the screen!

Style option pictures

Most of the pre-designed garments have at least one style option. The styles are illustrated in the dialog boxes, to indicate what the designer had in mind with each option.

Choose your preference for each option, and then click the "Next" button (or the "Done" button, when you come to the last option).





If you change your mind, you can go back to a previous page and make a different selection.


*Note: The style option pictures **do not** show a cumulative representation of your choices throughout the macro. Each set of images is only intended to illustrate the differences of that specific option. For example, consider the graphics above. If you had chosen "v-neck" on the previous page, you should not be alarmed when these pictures depict a jewel neckline, because this particular option page is only for choosing sleeve length.*

When you finish the style choices, your pattern will reflect your selections, even though the option pictures do not.

Measurement pictures

After you choose style options, it's time to enter measurements.

Each measurement is accompanied by an illustration, which shows you exactly where to measure, plus some explanatory text.




Replace the default numbers with your own measurements, then click the "OK" button.

If you have the Deluxe Editor or higher, you can save personal measurement tables and avoid typing in all your measurements for each pattern. See [Using Measurement Tables](#)⁴⁵, below.

Combining macro styles

You can mix style options from different macros, if one pattern has a particular feature you want to add to a different pattern. You can run more than one macro "on top of each other," and move or erase the pieces you don't need. Note that you may need to move some points to make sure that adjoining pieces will match properly if they are from two different macros. For example, if you want to add sleeves to a vest pattern to make a weskit blouse, you'll need to make sure that the armscye of the vest matches the armscye of the pattern that the sleeves came from.



In the illustration above, the points of the vest (black) need to be moved to match the blouse (red).

Related topics:

[Working with points](#)⁷⁰

Using Measurement Tables

You can save your measurements in a table that can be reused in other macros. This saves you from having to type in the measurements each time a macro is run.

Note: Measurement tables are not available in the Basic Viewer. If you use the Basic Viewer, you must type in measurements each time a macro is run.

Each garment collection comes with a measurement "template" that demonstrates which measurements are required. This template has a file extension of ".mmt," or "master measurement table."

Measuring

Note: These measuring instructions apply only to the pre-designed garments from Finnish designer Leena Lahteenmaki. Other designers may require measurements to be taken differently. Please be sure to carefully read the instructions that come with each garment collection.

Measuring Chart for Leena's Women's Garment Collections

You will need:

- four pieces of 1" wide elastic
- a measuring tape
- something to drape around your neck -- a necklace or piece of string, etc.
- an assistant to help you measure

Do not try to take the measurements yourself! Ask someone to help you measure. Stand straight but relaxed while being measured. You will receive the best results if the measurements are taken over underwear only.

Place the elastic bands around your bust, waist, abdomen, and hips. Keep the elastic bands on their correct places during the whole measuring process. Search carefully for the correct places of these bands. Hip elastic should be placed at the level where the hip circumference is greatest. Examine whether this is at the buttocks (7-8 inches/18-20 cm below the waist) or at the top of the thighs (10-12 inches/25-30 cm below the waist). Vertical measurements are taken from and to the bottom of the elastic bands. It is important to use the elastic bands throughout all measuring. Don't remove the elastic before all necessary measurements have been taken.

Do not tighten the measuring tape, as this will distort the measurements.

Except for pants' cuff circumference and skirt/dress length, all measurements are body measurements. DO NOT ADD ANY EASE to the measurements. The program does it for you. If you prefer to wear pants or skirts lower than your natural waist, take a second waist measurement at the location you want the waistband to fall. Make note of this second measurement for measurements 3, 12, 13, 17 and 18. For all other garments, you should use your natural waistline.

BE ESPECIALLY CAREFUL WHEN TAKING THE **MEASUREMENTS WRITTEN IN RED**. These are crucial for good fitting patterns. After you take all the measurements, take these important measurements again.

You can measure in either inches or centimeters. Make your measurements accurate to the nearest 1/4" or 1/2 cm

Name: _____

Date: _____


- 1 Neck Circumference: Measure around lowest part of neck, at the base.
- 2 Bust Circumference: Marked with elastic. Measure around the fullest part of the chest, keeping the tape high at the back.
- 3 Waist Circumference: Measure waist at the elastic tape
- 4 Abdomen Circumference: Measured at the level where abdomen circumference is maximum.
- 5 Hip Circumference: Measured over the largest part of your bottom/thighs (at elastic)
- 6 Bust Span: Horizontal distance between bust apexes (also called bust bridge). Measure along bust elastic.
- 7 Bust Height: Measure from apex of one breast, around back of neck, to apex of other breast. Divide the result by 2.
- 8 **Waist Height:** Measure from lower edge of waist elastic, straight up to breast apex, around back of neck, to other breast apex, and down to lower edge of waist elastic. Divide the result by 2.
- 9 **Back Length:** Put on a necklace or drape a piece of string around your neck. This marks the measurement location on the back of your neck. Measure from center of back neck to lower edge of waist elastic.
- 10 **Back Width:** Hang your arms relaxed at your sides. The measurement is taken horizontally between shoulder blades (i.e. from sleeve seam to sleeve seam), from and to the point where your arm meets your body (but not to the armpit) about 4" (10cm) from neck downwards.
- 11 Shoulder length: Measure from bottom of neck to shoulder tip. Shoulder tip is found when you raise the arm to horizontal position and feel where there is hollow/pit between shoulder and arm bones. Hold your arm horizontal, if necessary, to find this point.
- 12 Waist-Abdomen: Measure vertically from lower edge of waist elastic to lower edge of abdomen elastic. Measure at front center.
- 13 Waist-Hip: Measure vertically from lower edge of waist elastic to lower edge of hip elastic. Measure at the side.
- 14 Biceps Circumference: Measure at the widest point of upper arm.
- 15 Wrist Circumference: Measure over wrist bone.
- 16 Overarm: Arm length from shoulder tip (as described above) to wrist. Bend arm slightly and measure over outside of elbow.
- 17 Outside seam: Measure from waist over the outside curvature of the hip to the desired cuff length. This can be varied to create anything from shorts to full-length pants.
- 18 **Crotch Depth:** Sit on unpadded bench or chair. Measure vertically from waist elastic to chair level on both sides, and use the longer measurement. Measure in a straight vertical line, not along the outside hip curve. (Crotch depth can also be figured from an old, well-fitting pair of pants. It is the difference between outside and inside length of pants.)
Desired cuff circumference (not ankle circumference). This may change from garment to garment.
Desired jacket length from waist elastic to hem. This may change from garment to garment.
Desired skirt/dress length from waist elastic to hem. This may change from garment to garment.

IMPORTANT THINGS TO TAKE INTO CONSIDERATION WHEN MEASURING

Most important measurements are:

- waist height (from back neck over bust apex to front waist)
- back length (from back neck to back waist)
- back width (horizontal measurement between shoulder blades i.e. from sleeve seam to sleeve seam at a level of about one hand's width below neck)
- pants' crotch height (difference between pants' leg outside and inside length); this can be measured from a pair of old, well fitting pants

If one of these four measurements is wrong, the result may be a distorted pattern and it is difficult to figure what measurement is wrong. If some other measurement is wrong, you get either a too-tight or a too-loose garment and you can easily see what measurement to correct and to what direction.



Normally the pattern for basic sloper is more or less like picture 1. Front and back shoulders slope downwards to shoulder tip. Armscyes curve inward. Back armscye can be rather straight but should never bulge outward.

If the pattern looks like picture 2, i.e. front armscye curves strongly inward (a) and back armscye bulges outward (b), back width has been measured wrong and is too much. Take the back width measurement again. Please note that this measuring error causes the garment to be too loose at back and too tight at front. Therefore the situation cannot be corrected by only reducing width of back piece. The pattern must be redrawn using the correct back width measurement.

If waist height in relation to back length is wrong (refer to picture 3), the result is either a shoulder that slopes to wrong direction (3a), or a shoulder which is too steep (3b). If you measure waist height as instructed in PatternMaker measuring instructions i.e. double around back neck and divide the result by 2, there seldom is any error in waist height. Therefore the error usually is in back length.

If shoulder slopes in wrong direction, either: (a) back length is too much and if shoulder is too steep (b), back length is too little. Change back length 2-3 cm in the needed direction and see if it is enough to correct the situation. If it looks good, you can see at which point at the back of the neck the measurement should be taken to be correct.

If the subject stand in a very upright, military position with bust out and abdomen in, also waist height may be too much. Please make sure that the subject stands in a relaxed position (although not slouched) when she is being measured.

In some cases a steep shoulder may be due to the subject's body shape. This is the case if the subject has a very prominent bust. And conversely, if a subject has a very flat bust and/or a very round back, the shoulder can be rather straight.

Thus, there are cases, where the patterns are all right even if they look "odd". When the patterns are drawn according to a person's own measurements, they should not be compared with patterns drawn according to "normal" or "average" measurements. If you are not sure of the measurements taken, you have a very good and simple way to check them: sew a muslin with the basic bodice patterns. If it fits on the subject, you can be sure that all other garments sewn with Leena's patterns will fit well.

If you get an error message:

```
value out of range in line ...  
coord (32,33,sqrt(op*op-oke*oke),-oke);
```

it means there is a measuring error so drastic that the program is unable to draw the patterns at all. Front shoulder does not meet armscye line. Then either back length is too little or waist height too much. It may also be that shoulder length has some influence: shoulder length may be too short.

Also, in some other cases there may be reason for checking shoulder length measurement. If shoulder is too short, there will be a corner inward where front and back shoulder meet at shoulder tip and vice versa.

Setting up a measurement table

Set up a measurement table by selecting "Create Measurements" from the **Settings** menu.

- Each designer provides a "master measurement table" that acts as a template, indicating which body measurements are required for his or her designs.
- Select the **.MMT** file provided by the designer whose macro you are planning to use (the name of this file will be provided in your macro instructions).
- Enter your name at the top, and replace the default numbers with your own measurements.
- Save the table. Your new table is saved with an **.MTB** extension, so you can never accidentally overwrite the original template file.

See also:

[CREATE MEASUREMENT TABLE command](#)^[144]

Use your measurement table in a macro


- Click on the "MAC" icon




The **Macro** LaunchPad opens.

- Choose the designer *Leena* and the collection *Free Stuff*.
- For this example, we'll use the free Ladies' pants pattern. Select the file called "Pants - pleats or darts" and click the "Open" button.

III: Patterns and Printing



- This will launch the pattern. As the macro runs, you will be asked to select various garment options. For this example, it doesn't matter what options you choose; just click the "Next" button to move through the choices.
- At the end of the style options, the **Measurement** LaunchPad opens. This is where you select the measurement table you want to use.



- The measurements within the table will be "plugged into" the macro as it continues to run.

Too many measurements?

If the measurement table contains more measurements than are needed (as in this example with the pants), the extra measurements are simply ignored.

Not enough measurements?

Some macros will display a measurements dialog box even if you have used a measurement table. These are garment options that depend on numbers other than body measurements, such as the length of pant legs, or the flare of a skirt. These options can change from garment to garment, while the body measurements remain the same.

Changing a saved measurement table

If you need to make changes to a measurement table, use the "Edit Measurements" command on the **Settings** menu.

- An Open File dialog box will appear. The files are automatically filtered to show only the .MTB files.
- Select the table you wish to edit, and click the "Open" button.
- The table opens with the existing numbers.
- Change the numbers that need to be modified, and then click the "OK" button. The table is saved with the changes.

When you click "OK," your changes are automatically saved to the same table. If you want a second table with the new measurements, copy the measurement table first, then edit the new copy.

See also:

[EDIT MEASUREMENT TABLE command](#)^[145]
[COPY MEASUREMENT TABLE command](#)^[146]

3.2 Fabric yardage and pattern layout

Estimating Fabric Yardage

PatternMaker can help you with the calculations in determining yardage, but it is still up to you to make certain decisions, such as how many times each piece will be cut, which pieces need to be placed on a fold, and whether the fabric will be laid out in a single or double layer.

After you [define a fabric width](#)^[52], the yardage grid will display a rectangular shape that is as wide as the number you entered. The yardage is represented in the drawing area by a red dotted/dashed line.

Note: Turn the yardage grid on and off with the <CTRL>+<F12> shortcut key. You can also change your Configuration settings to determine whether the grid is on or off by default when you open the program.

Keep in mind that the initial arrangement of pattern pieces drawn by the macro will not represent a realistic fabric layout arrangement. You will need to use some of the editing commands to move the pattern pieces into a more practical arrangement.



The yardage grid will automatically change shape as you arrange pattern pieces and add objects to your drawing.

See also:

[COPY command](#)^[119]
[MOVE command](#)^[118]
[ROTATE command](#)^[122]


Define fabric width

From the **Settings** menu, select "Configure Program Options," and then click on the *Program Settings* tab. In the field labeled "Bolt Width," enter the width of fabric you wish to use. If your pattern pieces will be laid out on double layers of fabric, enter half the fabric width in the Bolt Width field. (For example, if your 60" fabric will be folded in half, enter "30" for the bolt width.)



Hint: Try your pattern layout with various bolt widths to see which gives you the best result.

After you define a fabric width, the yardage grid will display a rectangular shape that is as wide as the number you entered. The yardage grid is represented in the drawing area by a red dotted/dashed line. Turn the yardage grid on and off with the Hot Key <CTRL>+<F12> or use the check box on the *Program Settings* tab of the Configure form (found on the **Settings** menu).





Arrange pattern layout


Keep in mind that the initial arrangement of pattern pieces drawn by the macro will not represent a realistic fabric layout arrangement. Some pieces may overlap, and you will almost certainly find that one or more pieces extend past the first width of fabric.

Try these techniques to come up with an arrangement that works:

- Use the MOVE and ROTATE commands to move the pieces into a more practical arrangement.
- Use the FLIP commands to reverse the orientation of pieces as necessary.

Arrange your pattern pieces so that they fill one "width" and extend downward. The yardage grid will automatically change shape as you arrange pieces and add objects to your drawing.





Check the yardage indicator on the status bar to keep track of your fabric yardage.



3.3 Printing and assembling the pattern

How do you print a full-size pattern from just a desktop printer? It's simple! If the paper in your printer is too small to print an entire pattern, PatternMaker automatically breaks up the pattern into multiple pages.

Every page has alignment marks in the corners, to help you match the sheets together. Arrange the pages in rows and columns, and you have your pattern!

PatternMaker will work with any printing device, including ink-jet printers, laser printers, ink-jet or pen plotters, and even programs such as WinFax.

Keep in mind that the appearance of your printed pattern will vary slightly, depending on the capabilities of your printer. For instance, some printers only print black and white. Dotted lines may vary from printer to printer. Fill patterns also vary from printer to printer. PatternMaker attempts to make identical outputs on all printers, but this is not always possible. It should, however, be possible to assure that the patterns are always the same size, and very similar in appearance.

Printing Overview

When you have a drawing on the screen that you want to print, begin with these simple steps:

Select your printer:

Select "Print Setup" from the **File** menu. From the drop-down list, select the printer you want to use. If you want to install a new printer, you must do so prior to this step. (See your printer manual or Windows manual for details on how to do this.) When you select a printer, your choice stays in effect for your entire PatternMaker session.

Decide what you want to print:

- *Whole Drawing* – Use the [PRINT command](#)^[109] to print all the visible objects in your drawing
- *Selected Objects* – Use [PRINT SELECT](#)^[110] to print only certain objects
- *Selected Area* – Use [PRINT REGION](#)^[111] to print a rectangular-shaped section of the drawing


Preview the print job:

[Continue...](#)^[56]

Page layout grid

Note: The Page Layout Grid replaces the Print Area feature found in earlier versions of PatternMaker.

The page layout grid, shown as blue dashed lines, shows how your pattern pieces will be positioned on the sheets of paper when the pattern is printed. If a critical element (such as a grainline or notch) falls on a page intersection, you will know ahead of time that you should move the piece to avoid this situation. You can also use this grid to arrange your pattern pieces to make the most efficient use of paper. Use the MOVE, ROTATE and other editing commands to move the pieces to the best position.



The page grid is automatically sized to represent the printable area of your paper. These grid blocks represent sheets of paper arranged in rows and columns. The lines will change if you change your paper size, or if you switch from portrait to landscape orientation. The printable area is determined by the paper size you are using and the abilities of your printer.

III: Patterns and Printing

You can turn this grid off and on with the <F12> shortcut key, and you can change your Configuration settings to determine whether the grid is on or off by default when you open the program.


See also:

[TOGGLE PAGE GRID command](#)^[135]

[Configure Program Options: Program Settings](#)^[147]

Print Preview

With Version 7, PatternMaker introduces an entirely new Print Preview interface.



When you select any of the "Print" commands, the Print Preview window opens automatically. The blue dotted lines correspond to the page grid in your drawing area (see [TOGGLE PAGE GRID](#)^[135]). This shows you how many pages are necessary to print the entire pattern.

In the Print Preview window you can:

[print one specific pattern piece](#)^[110]


[print specific sheets of paper](#)^[56]

[print a scaled pattern](#)^[57]

[print a pattern layout diagram](#)^[59]

Select/unselect pages to print

Unshaded pages will be printed; shaded pages are not printed. Click on a specific page to switch between selected and unselected.



Notice how the "Select All" button toggles to "Unselect All" when you click it.

Back to [Print Preview](#) ⁵⁶

Print scaled pattern




Sometimes you might want to print a half-scale or quarter-scale pattern, for testing or some other special purpose.


The Print Preview window gives you a very simple way to accomplish this.

When you first enter the Print Preview window, your pattern is shown at full size:

III: Patterns and Printing



Select the print scale you want to use. You can choose one of the standard scale options or type your own number.



The page grid lines will change to reflect the new size of the pattern pieces.


Note: These scale options do not affect the size of your pattern in any way. This feature only changes the printed size.

Back to [Print Preview](#) ⁵⁶

Print setup

If you don't like what you see in the Preview window, there are several things you can do:

- Move the pieces in the drawing window. Use the [Page Grid](#) ⁵⁵ to help with the arrangement.
- Switch to a different printer, which may offer different paper-handling capabilities.
- Change your printer from Portrait to Landscape mode




You can access Print Setup by using the button on the Print Preview screen, or directly from the **File** menu.

Back to [Print Preview](#) ⁵⁶


Printing to a single page

This feature automatically reduces the entire drawing to the size of one printed page and prints it.

III: Patterns and Printing




You can also choose to include the yardage grid in your printout. This gives you a handy pattern layout diagram to file with your pattern or take with you to the fabric store.




Back to [Print Preview](#) ⁵⁶

Print options


On this part of the form you can choose certain things about the appearance of your pattern printout.



By default, each printed page has a label in the lower left corner, and alignment marks in each corner:



You can use these print options to disable the alignment marks (print page labels only)...



...disable page labels (print alignment marks only)...



...or disable both options.



If you have a printer that can use banner or continuous-feed paper, you may find it convenient to

III: Patterns and Printing

print column-by-column, rather than row-by-row (note how the result will change if you switch from landscape to portrait orientation).

Back to [Print Preview](#)⁵⁶

Putting pages together

Rows/Columns:

Each page that you print can be labeled, if you so choose, with alignment marks and row/column indicators. Together, they help you assemble your multi-page pattern quickly and easily. The name of the file being printed is also included. The row and column indicators tell you where a particular sheet of paper should be placed in the layout. Rows run across the drawing from left to right, and columns run from top to bottom.

	COLUMN 1	COLUMN 2	COLUMN 3
ROW 1	row 1 of 2 column 1 of 3	row 1 of 2 column 2 of 3	row 1 of 2 column 3 of 3
ROW 2	row 2 of 2 column 1 of 3	row 2 of 2 column 2 of 3	row 2 of 2 column 3 of 3

The pages are printed in order (either in rows or in columns -- see illustration below), so if you assemble them straight from the printer, you will find that it is an easy task to keep them organized. Align the pages as described below, and tape them together. It is better to have too much tape than too little, but you must at least apply tape at the points where the border of a pattern piece crosses from one page to another.

Order of printing (in rows):

1	2	3
4	5	6


Order of printing (in columns):

1	3	5
2	4	6

Of course, if you are using a plotter, or a printer that uses continuous-feed paper, you will have much less taping to do.

Aligning Pages:

Each page will have small marks in the corners for alignment (see illustration below left).



Each corner of the page represents one-quarter of a circle. Put the corners together with the adjoining pages so that each four-page intersection forms a circle with an "X" inside. Every four-page intersection should resemble the illustration (above right).

If you choose to have the pages labeled (the default is Yes), they will be labeled with the file name, row and column number so you will be able to assemble them easily.

See Commands Reference:

[PRINT command](#)^[109]

[PRINT SELECT command](#)^[110]

[PRINT REGION command](#)^[111]

Section

IV

Drawing and editing

4.1 Working with objects

How do you create a pattern with PatternMaker? You can open an existing file containing a drawing, or you can use a pre-designed pattern to draw it for you. But the way to create your own patterns, or to edit an existing one, is to use PatternMaker's many drawing commands to make new objects. These commands are designed to allow you to do the same things you would do in creating a pattern on paper: to "trace" an existing pattern with a digitizing pad, to measure distances and draft shapes to certain measurements, and so forth.

Types of Objects

Your PatternMaker drawing is made up of objects. For example, a bodice piece outline is an object, the arrow showing the grain line is an object, and the label that says "Front Bodice" is yet another object. PatternMaker handles objects slightly differently than most CAD programs, but you should find them easy to understand.

Each object is made of one or more points. This manual will usually refer to a point as a *vertex*. For example, if the object is a triangle, it will have three vertices – one at each corner. Objects have colors and other attributes, too, depending on the type of object. Many of these attributes can be changed with the CHANGE command or the various commands in the **Settings** menu (see [Configure/Configure Defaults](#)^[147]).

Each vertex may or may not have a grading arrow assigned to it. Grading and grading arrows are explained in Advanced Features: Grading Overview.

*Hint: The current layer must be turned ON for you to draw anything. If all of the **Draw** commands are inactive, and your version of PatternMaker is supposed to offer them, use the [LAYER](#)^[141] command to make sure the current layer is turned on.*

PatternMaker has four types of objects:

Text object

A text object is words, numbers, etc. that you can use as a label in your drawing. Text labels can be very useful in printed patterns, to identify pieces, pattern, material requirements, and the author/designer.

A text object has one vertex, which gives the location of the lower left corner of the text. You can print text in any size, at any orientation or angle, and in any TrueType font (typeface) that is installed on your computer.


Your PatternMaker installation includes a built-in font called "PatternMaker." This is the default font that will be used until you change to a different font, and it appears in the font drop-down box on the Status Bar (however, the PatternMaker font is not available in other Windows applications). The PatternMaker font draws text as if it were written with a single stroke of a pen (see example below.) All other Windows fonts will be drawn as an outline of each letter. Also, some printers may print the fonts slightly differently than they appear on the screen. Be sure to print a few samples of TrueType fonts before you use a lot of them.

This is the default PatternMaker font

This is Arial

This is Times New Roman

When you draw a text item, the computer will ask for a location, size, rotation angle and for the text to be printed. The size is the height in inches. The angle is measured in degrees, going counterclockwise. For instance, 0 degrees is horizontal, and 90 degrees is vertical, reading upwards.



Hint: If you want to have multiple lines of text, make several text objects. One of the easiest ways to line them up is to turn on Snap to Grid and then line up the text on grid points. For example, if you are drawing text that is $\frac{1}{4}$ " tall, set the grid to $\frac{1}{2}$ ", or .5, which will then be the spacing for your text items.


See also:

TEXT command

Dimension object

A dimension, or "dim," object is an engineering-style dimension line, showing the distance between two points. This consists of lines and arrows indicating the two points at which the measurement is taken, and the distance between the points.

A dimension object has three vertices: the two points being measured, and one to indicate where to print the numbers. If you move one end of a dimension line, the distance will automatically update.



Dimension object

See also:

[DIM command](#)  ₁₁₄

Drawing an object

The **Draw** menu contains the names of several different objects that you can add to your drawing. Some, such as Line, Circle, and Offset, are actually polygons themselves, but they have separate command names to make them easier to access and create.

The Polygon is the most common type of object that you will use. This is the basic order of events in drawing a polygon:

- Select the POLY command
- Enter some points
- Choose options from the Poly sub-menu
- Enter more points
- Choose "Done" from the Poly sub-menu

See the POLY command for detailed instructions on drawing polygons.

Editing objects

The Edit commands all follow a similar routine: first select a command, then give the computer the information it needs to execute the command. For instance, for the MOVE command, here's what you do:

1. Select the MOVE command.
2. Tell it *what* to move.
3. Tell it *where* to move.

During steps 2 and 3, you are "in" the MOVE command. You can't give any other commands, except the Hot Key or icon commands, until you are out of the MOVE command. When you start another command, you will need to select a new set of objects.

Note on Commands and Objects:


In PatternMaker you select commands first and then the objects they apply to. Some programs work like this, some are the other way around.

See also:


[Activating a command](#)  ₂₉

Base point and destination

Many commands will ask you to specify a "base point" and a "destination." The base point is like a handle that you use to carry the object(s). The destination is, of course, where you want the object(s) to end up. The base point and the destination are the reference points used for performing the command. For example, for the MOVE command, the distance the selected objects will be moved is equal to the distance between the base point and the destination point.



Note: It usually doesn't matter what spot you pick for the base point. Just click wherever it's convenient.




Move the mouse around until the object is where you want it.


Using typed coordinates is especially useful for specifying the destination point. Sometimes it doesn't matter how far you move something – you just want it out of your way. But if you need to move an object a certain distance, you can use [Relative Coordinates](#)³⁶ to do it accurately.

Example: the MOVE command

1. Draw a line using the LINE command in the **Draw** menu, or using the "Line" icon in the icon area. Try to make the line look something like this:




2. Now select "Move" from the **Edit** menu. The bottom line of the command area will say: Select object, ? for help, <ESC> = done:
3. You can press <ESC> to cancel the command, or press <?> to get help. For now, answer this question by clicking on the line. It will highlight.




The same prompt will be repeated, giving you a chance to select more than one object. This time, since you are done selecting objects, respond by clicking the right button of the mouse.

4. Now the computer will respond with a new question: **Base point?**: The base point is the "handle" you will use for moving the object. It is often convenient to carry a line by the midpoint, so click somewhere in the middle of the line you are moving.
5. After you click, the prompt line will say: **Destination:** Move the mouse around and you will see the line move.



6. Move the line around a bit. Notice the cyan (bluish) line that shows you how far the line has moved.
7. Click the left button again to place the line in a new position. The final result should look like this:



Note: You can also use typed coordinates in Step 6 to move the line a specific distance or at a specific angle. See [X and Y coordinates](#)^[34] for details.

4.2 Working with points

You need to enter points any time you draw or edit anything with PatternMaker, and also when you are selecting objects or vertices. PatternMaker offers three ways to enter points: mouse (with or without a Snap mode), typed coordinates, or a digitizer.

Using a mouse

You can click in the drawing area to enter a point. Use the left mouse button (**LM**). This is the simplest way to enter data, but it may not be as accurate as you want.

Using a mouse with Snap modes

Snapshots are a way to make mouse inputs more precise. See [Using Snap modes](#)^[32] for more information.

Using typed coordinates

You can indicate a point by using X/Y coordinates. See [X and Y coordinates](#)^[34] for more information.

Using a digitizer

If you are using a digitizer, the puck can be used to enter points, just like a mouse.

Types of points

Whether a segment of a polygon is a straight line or a curve depends on the type of the point at the start of the segment. There are four types of points:

- **Line (L)**
Ordinary points are connected by straight lines. In other words, a Line point is a corner of a polygon.
- **Arc start (X)**

The beginning of an Xarc (see below).


- **Arc corner (C)**

This is the corner point, or control point, of an Xarc (see below). This point controls the shape and amount of curvature of the Xarc. If you use the MOVE VERTEX command to move a corner point, you will see how the arc changes shape.

Since the corner point doesn't lie on the object, it will sometimes be difficult to tell exactly where the corner point is. Use the <F5> Hot Key to display the vertices if this happens.

- **Open (O)**

An open point is the last point of an open polygon. Only the last point of a polygon can be of the Open type. This is how PatternMaker tells the difference between an open and a closed polygon.




Drawing curves with x-arcs


Xarcs are the way PatternMaker draws curves. While a line segment is determined by two points (start point and end point), an Xarc is determined by three points: the start point (type X), the corner point (type C), and the end point. The end point can be the start of a line, the start of another Xarc, or the end of the object.

The corner point determines the shape of an Xarc. If you draw an imaginary line from the corner point to one of the end points of the Xarc, the line will blend smoothly into the line of the Xarc (will be "tangent" to the line). This means that:


- If the corner point, the end point, and the next point after that all lie on a straight line, the Xarc will merge smoothly into the next segment of the object.



This is true whether the next segment is a straight line or another Xarc. A sleeve cap, for example, will consist of several curves that all need to merge smoothly.



- If the corner point, the end point, and the next point of the object form a right angle, then you will get a square corner where the arc meets the next segment of the object. This is the common procedure for curved lines such as arm and neck holes.



These two facts are important to keep in mind as you adjusting the shapes of curves in your drawings.

Hint: If you can't get an Xarc to take the exact shape of the curve you want, such as for an arm hole, draw the curve as two or three Xarcs together.

Editing points

The Point Edit commands are used on individual points of objects, rather than whole objects at a time. You can move, add, delete etc. The vertices don't all need to belong to the same object, and the rules are similar to the rules for selecting objects (see [Selecting objects](#)^[30]). The general order of events is:

1. Select a command (such as MOVE VERTEX).
2. Select the vertex or vertices to apply the command to.
3. Give PatternMaker any other information (for MOVE VERTEX, this would be first the point to move from, then the point to move to).

Base point and destination

Many commands will ask you to specify a "base point" and a "destination." The base point is like a handle that you use to carry the object(s). The destination is, of course, where you want the object(s) to end up. The base point and the destination are the reference points used for performing the command. For example, for the MOVE VERTEX command, the distance the selected objects will be moved is equal to the distance between the base point and the destination point.

Note: It usually doesn't matter what spot you pick for the base point. Just click wherever it's convenient.


Using typed coordinates is especially useful for specifying the destination point. Sometimes it

doesn't matter how far you move something – you just want it out of your way. But often you need to move an object a certain distance. Use [Relative Coordinates](#)³⁶ to do this accurately.

Example: the MOVE VERTEX command

1. Start out by drawing a square (RECT command). Select "Move Vertex" from the **Point** menu. The program will ask you for a point to be moved. The prompt says:
Select point(s):
2. Select the upper right corner of the square by clicking **LM** on it. Then select the lower right corner by clicking on it also. The program will highlight both points.


Your drawing will look something like this:



The 'x' marks on the two corners mean these points have been selected. Click **RM** to indicate that you are finished selecting points.

3. The computer will now ask:
Base point:

This means it wants to know where to start the move. Click anywhere on the right side of the rectangle as shown below.




The computer responds by saying:

Destination:

4. Now move the mouse a little to the right. You will see the outline move with the mouse, distorting the shape of the square. A cyan (bluish) line appears, showing the distance of the move. When you get the points where you want them, click the mouse.

Your shape should look something like this:



Adjusting arc lengths


Use the Set/Measure Dist. function to adjust the length of a curve or a section of an object. You can select any two non-adjacent vertices of an object, and PatternMaker will give you the length of the section connecting them. You can adjust the length by typing in a new value for this distance. PatternMaker will move the vertices along the selected section to adjust the distance. The endpoints of the selected section will not move.

Example: Use Set/Measure Dist. to make sure that your armscyes match your sleeve caps. Remember to allow for seams and ease.

Note: Adjust armscyes, neck holes, and other curves with standard patternmaking methods. The MOVE VERTEX command is very handy for this. Then use the Set/Measure Dist function to make fine adjustments to a curve. Set/Measure Dist works best for adjustments of ½ inch or less.

Note: This command only works when you select a segment with at least three vertices. Therefore, you cannot use this command to adjust the length of a line with only two vertices (although you can still check the measurement).

Section



V

Going Further

5.1 Customizing PatternMaker

Main drawing window

There are many ways you can set up the main PatternMaker window in order to make it work effectively for you. Panels, grids, and Hot Keys can all be customized the way you want.


Set measurement units

This setting selects the units of measurement, either inches or centimeters. If you select either of the metric displays (meters or centimeters), all PatternMaker input and output will be in centimeters. If you select any of the English units, all input and output will be in inches. To see which units are in use, look at the X-Y coordinates in the status bar.

When you change this setting, all Dimension objects are redrawn with the new units and the grid (if you're using it) is resized.

Procedure:

1. Click the mouse coordinates box on the Status Bar, or select "Configure" or "Configure Defaults" from the **Settings** menu to open the "Program Options" form.



2. Choose one of the following options:

Option	Description	Example
inches, no fractions	The measurement is in inches, fractions are in decimal form. No " symbol is displayed.	18.375
inches	Measurement is in inches. Fractions are in decimal form.	18.375"
feet + inches	Fractional inches are written as fractions	1'6-3/8"
meters	The measurement is in meters	1.462 M
centimeters	The measurement is in centimeters	1462 cm

Set grid spacing

This setting adjusts the grid spacing. The spacing is measured in whatever units (inches or cm) you are using.

Procedure:

1. Select "Configure" or "Configure Defaults" from the **Settings** menu. The "Program Options" form opens.
2. The "Alignment Grid" section displays the current spacing between grid points.



3. To change the grid spacing, you must turn the grid on. Type the number you want, and then click the "OK" button to the drawing screen.

See also:

[Set measurement units](#) ^[76]


[SNAP commands](#) ^[140]

[TOGGLE GRID command](#) ^[135]

Show/hide Page Grid

The PAGE GRID option is accessed by a field on the *Program Settings* tab of the "Configure" or "Configure Defaults" form, found on the **Settings** menu.

This setting shows or hides the page layout grid. This is also an option on the **View** menu, or you can use the <F12> hot key.



The size of this grid is determined by the size of the paper you are using in your printer. It displays the actual printable area, not the paper size. A change of printer or a different paper size will affect the appearance of the page grid.


See also:

[Page layout grid](#) ^[55]

[PRINT command](#) ^[109]

Show/hide Yardage Grid

This option is accessed by a field on the *Program Settings* tab of the "Configure" or "Configure Defaults" form, found on the **Settings** menu.



This setting toggles the yardage grid on and off. This can also be toggled with the <CTRL>+<F12> hot key.

See also:

[Set fabric width](#) ^[78]

[Estimating Fabric Yardage](#) ^[51]

Set fabric width

This option is accessed by a field on the *Program Settings* tab of the "Configure" or "Configure Defaults" form, found on the **Settings** menu.



In the field labeled "Fabric Width," enter the width of fabric you wish to use. If your pattern pieces will be laid out on double layers of fabric, enter half the fabric width in the Bolt Width field.

Example: You are using 60" fabric, but plan to fold it in half for the fabric layout. Enter "30" for the bolt width.

See also:


[Show/Hide Yardage Grid](#) ⁷⁷
[Estimating Fabric Yardage](#) ⁵¹

Right-click context menus




These context menus have been added to provide guidance while you're getting used to the left-click/right-click circumstances in PatternMaker. If you accidentally right-click when you should left-click, the context menu guides you toward the correct choice. You can also access Help for the selected command.

If you're using a command with just one step, such as a drawing command, the context menu will let you either cancel the command or keep drawing.



If the command involves selecting things, the menu is slightly different. It will let you cancel the command, continue selecting, or indicate that you are done selecting.




If you no longer want to use these context menus, the control setting is available on the "Configure" or "Configure Defaults" form on the **Settings** menu.



Set background drawing color


This setting changes the drawing area from white to black. The default is white, but you may find the colored vertices easier to see against a black background.

Select "Configure" or "Configure Defaults" from the **Settings** menu, then click the *Program Settings* tab. If you only see a few options on the form, click the "Advanced" button at the bottom. Then click in the "Use White Background" check box to turn this option on or off.




Moving the command line

The default configuration of PatternMaker has the blue command line positioned at the bottom of the screen:



If you wish, you can move the command line to the top of the screen, right under the Status bar. Some users find it easier to keep an eye on the command prompts when the command line is in this position.



Procedure:

- Click in the blue area of the command line and drag the panel up to the top of the screen.
- If you can see the borders of the panel when you release the mouse button, it's not in the right place. Try moving it a little bit up or down. The icon bar will automatically be moved down when the command line is in the correct position.
- The command line will remain in its new position each time you open PatternMaker until

you move it again.

Show/hide ID Object Panel

The ID Object panel provides information about objects, points, and text objects. Check this panel for information about something on the screen if you have several things near each other and can't tell them apart.



You can turn on the ID Object Panel either from the "Configure" or "Configure Defaults" form or with a checkmark on the **View** menu.

See also:

ID OBJECT PANEL

Configuring floating windows

The iconbar and the command line area can be turned into "floating" panels or windows.

Procedure:

1. Make sure the PatternMaker window isn't at full size (ie, taking up the whole screen).
2. Click on a clear area in the pane and drag the panel outside the PatternMaker window. Note that you can't perform the drag and drop by dragging an icon in the icon pane. You must click in a clear area.

To return the pane to its normal position, drop it inside the Patternmaker window.

If you shut a pane, you can restore it by going to Settings->Configure->Status Bar and checking either "Icon" or "Prompt" under *Show Panels*.

Configuring Hot Keys



This feature gives you the option of reprogramming the standard Hot Key assignments. If you find the <Ctrl>+<F> combinations too awkward for using the Snap modes, feel free to change them to something more convenient!

You can also save different sets of Key assignments, in case you'd like to use different keys depending on what you're doing.

The Hot Key configuration files are saved in the user settings for each profile on the computer. This means that everyone who logs on to the computer can save the Hot Keys the way they like them best. You can also move your configuration file to a different computer.

See also:

[Configure Program Options: Hot Keys](#)  ¹⁵³

Customizing the icon bar

When you install PatternMaker, there are certain icons visible on the icon bar. These represent some of the most commonly-used commands. However, there are far more icons available than there is room on the icon bar. So, you can choose to hide some of the default icons and turn on the icons for your favorite commands. The number of icons you can fit on the icon bar is limited only by the size of your screen.

Not all commands have icons, but most do. The available icons can be seen next to the command name on the menus.

You can also attach your favorite macro to a button, or a command that doesn't already have a specific icon. There are 20 custom icons that you can use for buttons that otherwise have no picture.


See also:

[Configure Program Options: Icon Bar](#)  ¹⁵²

Setting drawing preferences

Several of the most frequently used drawing options are available as drop-down boxes on the status bar; all those as well as other options can also be accessed from the "Configure/Configure Defaults" form.



**See also:**

CHANGE OBJECT command
[LAYER command](#)^[141]

Configure: COLOR

This command selects a color for any new objects that are added to the drawing. It does not change the color of any existing objects. The color selection affects both the line color and the fill color.

There are several ways to change the drawing color:

Status Bar:


Use the "Line Color" drop-down box on the status bar, and select a new color as described below.

**Color Icon:**

Activate the COLOR command by clicking the Color icon, and choose a new color as described below.

**Configure Form:**

Use the "Line Color" field on the *Program Settings* tab of the Configure form. The Configure form is found on the **Settings** menu. Select a new color as described below, and then click the "Okay" button on this form to return to the drawing screen.




Choosing a color:

Regardless of which method you use, you will then see a dialog box:



You can choose either the [default layer color](#)^[101] or any custom color. If you want a custom color, click the "Select" button, and the standard Windows color dialog box will open.



If you choose any color other than the layer default, your choice will override the default layer color. Any object that you draw after making this change will be in the color you selected, regardless of the layer's default color.

Make your color selection and then click the "OK" button to return to the drawing screen.

Note: To change the color of an object that has already been draw, use the CHANGE OBJECT command.

See also:

[Default layer colors](#)¹⁰¹

[Configure defaults](#)¹⁴⁷

CHANGE OBJECT command

Configure: PATTERN

This command selects a new fill pattern for any new polygon objects that are added to the drawing. It does not change the fill pattern of any existing objects. The fill pattern will always be the same color as the object itself.

There are several ways to change the fill pattern:

Status Bar:

Use the "Fill Pattern" drop-down box on the status bar and select a fill pattern as described below.



Pattern Icon:


Activate the PATTERN command by clicking the Pattern icon, and choose a fill pattern as described below.



Configure Form:


Use the "Fill Pattern" field on the *Program Settings* tab of the Configure form. The Configure form is found on the **Settings** menu. Select a fill pattern as described below, and then click

the "OK" button on this form to return to the drawing screen.



Choosing a fill pattern:

Regardless of which method you use, you will then see a drop-down menu or a dialog box:



There are eight options for the fill style: six patterns, plus "solid" and "empty." The selection at the top is the current pattern (the default is EMPTY, which draws unfilled objects). Below are samples of the 8 fill types. After you make a selection, it remains in effect until you change it again, or until you restart PatternMaker.

To change the fill pattern on an object which you have already drawn, use the CHANGE OBJECT command on the **Edit** menu.

Note: Not all printers handle filled objects the same way. Make sure yours prints the way you want before you use very many different fill patterns.

See also:

[Configure defaults](#)¹⁴⁷

CHANGE OBJECT command

Configure: FONT

The FONT command is used to select a new font style (typeface). When you draw new Text objects, they will use this font. To change the font of an existing Text object, use the CHANGE FONT command on the **Edit** menu.

There are two ways to change the font:


Status Bar:

Use the "Font" drop-down box on the status bar. Select the font you want to use.



Configure Form:

Use the "Font" field on the *Program Settings* tab of the Configure form. The Configure form is found on the **Settings** menu. Select the font you want, and then click the "OK" button on this form to return to the drawing screen.



Whichever way you do it, you will see a drop-down box with the different fonts that are available. You can use any TrueType font that is installed on your computer; however, keep in mind that they may not appear as you expect. All TrueType fonts will appear "hollow" (see the illustration below). To avoid this, use the default PatternMaker font.

This is the default PatternMaker font

This is Arial

This is Times New Roman

Print a test page before using very many TrueType fonts, to be sure you like the way they look in print.

After you choose a line style, it remains active until you change it again, or until you restart PatternMaker.

See also:

[Configure defaults](#)¹⁴⁷

CHANGE FONT command
CHANGE TEXT command
TEXT command

Configure: LINE WIDTH

This command sets the width of the drawing line. Every new object you draw will be drawn using the new line width.

There are two ways to change the line width:


Status Bar:

Use the "LineWidth" drop-down box on the status bar. Select the line width you want to use. This can be from 1 to 10.



Configure Form:

Use the "LineWidth" field on the *Program Settings* tab of the Configure form. The Configure form is found on the **Settings** menu. Select the line width you want, and then click the "OK" button on this form to return to the drawing screen.



Whichever way you do it, the drop-down box displays the current width at the top (the default is 1), with the other options below (with a maximum line width of 10).

After you choose a line width, that selection remains active until you change it again, or until you restart PatternMaker.

If you want to change the line width of an object you have already drawn, use the CHANGE OBJECT command on the **Edit** menu.

Note about line widths: The appearance of the printed lines depends on this line width setting *together with your printer settings*. When PatternMaker prints a pattern, it tells the printer to print everything "one dot" wide (or two dots, or five, or whatever you have selected). If your printer is set on a high resolution -- that is, lots of dots per inch -- the

dots are very small. If the printer is set on a lower resolution -- fewer dots per inch -- each dot is larger. The highest resolution (very small dots) is what you want for printing certain things, like photographs, but this can result in your pattern lines being too faint. If you encounter this problem, try changing your printer settings before changing the line widths of everything in your drawing.

See also:

[Configure defaults](#)¹⁴⁷
CHANGE OBJECT command

Configure: LINE STYLE

This command sets the current linestyle to solid line, dotted, dashed etc. Every new object you draw will be drawn using the new line style.

There are two ways to change the line style:


Status Bar:

Use the "LineStyle" drop-down box on the status bar. Select the line style you want to use.



Configure Form:

Use the "LineStyle" field on the *Program Settings* tab of the Configure form. The Configure form is found on the **Settings** menu. Select the line style you want, and then click the "OK" button on this form to return to the drawing screen.



Whichever way you do it, you will see a drop-down box with the different line types:



The pattern at the top is the current style. The default style is a solid line. Below are the five available types. After you choose a line style, it remains active until you change it again, or until you restart PatternMaker.

If you want to change the linestyle of an object which you have already drawn, use the CHANGE OBJECT command on the **Edit** menu.


Not all printers print these line styles the same way, so make sure they look the way you want before using them extensively.

See also:

[Configure defaults](#)¹⁴⁷
CHANGE OBJECT command

Configure: DOT WIDTH

This setting changes the size of the DOT pattern marking.



Procedure:


- Select "Configure" from the **Settings** menu, then click the *Program Settings* tab.
- If you only see a few options on the form, click the "Advanced" button at the bottom of the form.
- Enter a number in the "Dot Width" field.



The size of the dot is based on the [Measurement Units](#)⁷⁶¹ you have selected. If inches are selected, a dot size of .25 is 1/4 inch.

Configure: X-ARC PIECES

This setting controls the smoothness of the XArc curves. A higher number makes smoother curves, but in a large, complicated drawing it may make a noticeable difference in the program's response time.



The smoothness of the curves is far more apparent in the printed pattern than on the screen. You probably won't notice any difference in the on-screen curves until the number gets below 12, so if you find that your drawing is slow to refresh, try setting this number quite low until you're ready to print the pattern.

Changing this setting will affect all the existing arcs in your drawing. You cannot have a number of curves with different "XArc Pieces" values.

Procedure:

- Select "Configure" from the **Settings** menu, then click the *Program Settings* tab.
- If you only see a few options on the form, click the "Advanced" button at the bottom of the form.
- Enter a number in the "XArc Pieces" field. The default of 36 provides a good balance between speed and smooth curves.



Note: This setting only affects circles and curves drawn with the POLY command. It does not affect the number of segments in a COMPASS arc, nor the number of segments used for the [OFFSET LINES](#) ⁹³ option.


Configure: DIM SETTINGS

This setting controls how dimension objects are drawn.

Procedure:

1. Use the "Dim Settings" section of the *Program Settings* tab of the Configure form. The Configure form is found on the **Settings** menu.
2. The settings are:

Text Size	The size of the numbers, in "units" -- either inches or cm, depending on your settings.
Arrow Size	The length of the arrowheads.
Line Offset	The distance between the dimension lines and the actual points being measured, to keep the dimension line from getting in the way. The distance from the point being measured to the Dim line is 1/2 of the offset.
Dim Font	The typeface used for the Dimension words.



3. Enter the values you want, and then click the "OK" button. *The changes you make apply to all existing Dim objects, as well as ones created after you make the change.*

Note: The Dimension text size also determines the size of the names of grading arrows.


See also:

[DIM command](#)¹¹⁴

[Set measurement units](#)⁷⁶

Configure: OFFSET LINES

The OFFSET LINES command draws a curved line as a series of tiny line segments. There are certain circumstances in which this can improve the shape of an Offset object (seam allowance). However, if you choose this option, you can no longer change the shape of the curve by moving the corner control point, because there no longer is a control point. The Offset object can still be edited by moving the individual line segments, but it is vastly more difficult and laborious.



Note: Objects drawn with offset lines remain that way, even when you change the setting on the Configure form.

To toggle this setting on or off, select "Configure" or "Configure Defaults" from the **Settings** menu, and click the *Program Settings* tab. Click in the "Offset Lines" check box to turn this option on or off.



See also:

[DRAW OFFSET command](#)¹¹⁵

Menus and dialog boxes


This section covers several other menu and dialog box options that you can customize.

Choose LaunchPad vs Windows dialogs

One of the most fundamental choice in PatternMaker 7 is the option of using the new LaunchPad interface. This new feature has been carefully designed to help you easily locate your files and pre-designed garments, and save your pattern files without worrying about losing them.

The LaunchPad interface features a focus picture for every file, and explanatory text for all pre-designed garments. You can also save comments along with your own pattern files.

The LaunchPad interface is active by default. If you would prefer not to use it, you can turn it off by marking the "Use Windows Browsers" checkbox on the "Configure" or "Configure Defaults" form. If the box is checked, the standard Windows dialog boxes are used instead of the LaunchPad windows.



See also:

[LaunchPad interface](#) ¹⁸

Show/hide Start form

The Start form offers a quick way to choose the activity you want to do with PatternMaker.

The Start form is turned on by default when you first install PatternMaker. If you turn off the form, you can get it back with this setting on the "Configure" or "Configure Defaults" form.

Procedure:

- Select "Configure" or "Configure Defaults" from the **Settings** menu, then click the *Program Settings* tab.
- Mark or clear the "Show Start Form" checkbox.



See also:

[Start Form](#) ¹³


Set Start locations

This setting determines the default designer and garment collection that will be selected when you first choose the [MACRO command](#) ¹¹¹ upon starting PatternMaker.

Once you have navigated to a different collection or designer folder, the MACRO command will open to the last selected location. This makes it convenient to use one pattern several times, or use more than one pattern in a collection. But the next time you open PatternMaker, the Start folder will return to this default location.

Procedure:


- Select "Configure" or "Configure Defaults" from the **Settings** menu, then click the *Program Settings* tab.
- If you only see a few options on the form, click the "Advanced" button at the bottom of the form.
- Then click in the fields to select the desired location from the drop-down box.




Show Explorer tree

This setting toggles the Explorer tree in the LaunchPad windows.

Explorer tree is on:



Explorer tree is off:




The LaunchPad interface normally hides the locations of files, and instead directs you to a particular location that depends on the type of file you are opening or saving.

If you want to save a file in a different location, or if you simply want to know where the files are going, you can turn on the Explorer tree in the LaunchPad window. This provides a view of the standard Windows Explorer tree.

Procedure:

- Select "Configure" or "Configure Defaults" from the **Settings** menu, then click the *Program Settings* tab.
- If you only see a few options on the form, click the "Advanced" button at the bottom of the form.
- Mark or clear the "Show Explorer Tree" checkbox.



- There is also a checkbox on the LaunchPad form that does this same thing.

See also:

[Folders and file organization](#) ¹²⁷

Show shared files

This feature is primarily intended for those who share a computer with another PatternMaker user. It provides easy access to the folder where shared files are stored.


By default, program files and garment collections are installed to a location where all users can access them. Any file created by a user, on the other hand -- a saved pattern file, personal measurement table, grading table, etc. -- is saved in the user's "personal" folder. In most shared computing environments, these files will be inaccessible to other users.

In order to share a pattern file you've saved -- for example, a teacher who wants her students to alter a pattern she has designed -- it must be saved to the shared location.

If you need to save something in the shared location and the *Shared Files* tab is not visible, you can navigate to the shared location using the [Explorer tree](#)^[95] in the LaunchPad window.

Procedure:

- Select "Configure" or "Configure Defaults" from the **Settings** menu, then click the *Program Settings* tab.
- If you only see a few options on the form, click the "Advanced" button at the bottom of the form.
- Mark or clear the "Show Shared Files Tab" checkbox.



See also:

[Folders and file organization](#)^[12]

Set Undo history

This setting lets you specify how many [UNDO](#)^[117] steps you want stored in the computer's memory. This number can be anything you want; a higher number gives you more flexibility in retracing your steps, but it will make the program run more slowly.

Procedure:

- Select "Configure" or "Configure Defaults" from the **Settings** menu, then click the *Program Settings* tab.
- If you only see a few options on the form, click the "Advanced" button at the bottom of the form.
- Enter a number in the "Undo History" field.



Set File history

This setting lets you specify how many previous files you want displayed on the **File** menu. This number can be anything you want; a higher number just takes up more room on the menu.



Procedure:

- Select "Configure" or "Configure Defaults" from the **Settings** menu, then click the *Program Settings* tab.
- If you only see a few options on the form, click the "Advanced" button at the bottom of the form.
- Enter a number in the "File History" field.



5.2 Using Layers

Layers are an advanced drawing feature that help you organize objects in your PatternMaker drawings. Every object in your drawing is on a layer. When you turn a layer off, all of the objects on that layer disappear from the screen. You don't see them, they can't be selected, and you can't print them. When you turn the layer back on, the objects reappear.

Note: If you select an object that is grouped with other objects, those objects are selected as well, even if they are on layers that are turned off (see Using Groups). This is the only way to select objects in layers that are turned off.

Use the [LAYER command](#)¹⁴¹ to navigate from one layer to another. The CHANGE OBJECT command is used to change the layer of an existing object. Use the ID OBJECT PANEL to check what layer an object is on.

Example: Suppose your drawing contains several sizes. Put the pieces for each size on a different layer. Give the layers names such as Size8, Size10, etc. When you want to print Size10, use Layer to turn off all the other layers and then select the Print All command.


Example: Suppose your drawing contains many text items and the time it takes to display these on screen is slowing your computer down. Put all the text objects on one layer and turn it off until you need to see them.

You can assign your objects to layers any way you want, but normally you will want to put each size on a different layer because this is how the Grade command treats the different sizes.

The LAYER dialog box

The LAYER command is used to display and/or change the settings for the layers. These settings include their names, colors, and whether they are on or off (visible or hidden), as well as changing the active layer on which new objects are drawn. The LAYER command can be selected from the **Settings** menu or by using the <F11> Hot Key.

When you select the command, a large dialog box will come up with a display of the information for each layer. Each line represents a different layer. The current layer is represented with an asterisk. There are 24 layers, but they won't all be visible in the dialog box at once. Use the scroll bar to move up and down the list. You can change any of the settings by clicking the mouse on the item you want to change.




See also:

[LAYER command](#)^[141]
[Default layer colors](#)^[101]


Set the current layer

Any new objects you draw will be placed on the current layer.

You can change the current layer with the LAYER command (<F11> or the **Settings** menu). The current layer is marked with an asterisk and highlighted. Select a different layer by clicking in the "Current" column of the layer list. The previous current layer will be untagged, and the new current layer will be tagged. Close the Layer box by clicking the "OK" button.




The Status Bar has a "Layers" drop-down box that you can use as an alternate method of switching from one layer to another. However, you cannot change the name or color of the layer from this drop-down box.



Naming a layer


Each layer has a default name: "Layer0," "Layer1," "Layer2," etc.

You can change a layer's name with the LAYER command. Open the "Layer" dialog box either by pressing the <F11> Hot Key or from the **Settings** menu. Click on the name you want to change, and retype it. Click the "OK" button when you're finished.



Turning a layer on and off

You can turn a layer on and off with the Layer command. Just open the Layer box (<F11> or the **Settings** menu) and click on the word "on" or "off" next to the layer you want to change. When you are done, click the "OK" button.



Default layer colors

Each layer has an automatic default color, called "LayerColor." That's its name, just like the colors called "Red" or "Blue". The layer color is what determines the color of new objects that are added to the drawing. All new objects are drawn using "LayerColor" *unless* you specifically change the current drawing color or assign a different color to an object.

Examples:

- An object's color is "LayerColor" and it is on Layer0. The object is black (default color of Layer0). If you move the object to Layer1, the object turns green, because that is the default color of Layer1.
- Layer0 is active (default color black), and you change the drawing color to red and draw a shape. The new shape is red. If you move the object to Layer1 (default color green), the object is still red.

If you want to change the default color of a layer, any object on that layer with the color assignment of "LayerColor" will be updated to the new color. The settings for changed layer colors are saved in the internal file format when you save a drawing.

However, when you begin a new drawing, or when you start PatternMaker the next time, the settings revert to the default layer colors. You cannot permanently change the default layer color.

See also:

[COLOR command](#)⁸³
CHANGE OBJECT command

Assigning objects to a layer

When you draw an object, it is automatically drawn on the current or "active" layer.

Often you will draw things first, then decide later what layer to put them on. This is fine. If you have a drawing with some objects in it, and you haven't assigned them to layers, then they are probably on Layer 0. Use the CHANGE OBJECT command if you want to move them to a different layer.


Layer Lock



When a layer is locked, it means that its objects are visible, but cannot be selected or manipulated in any way. This can be useful if you need to trace an object, or compare one or more objects.

Reset Layers

If you click on the "Reset" button in the Layer box, all layer names, colors and on/off status will be set to the original values.



5.3 Types of files

Normally, when you open a type of file, the list that appears is filtered, to show you only the files that are of the type you are opening. (For example, when you are opening an ordinary drawing, you do not see the files that contain grading tables, or the font files.) However, if you look at the PatternMaker folder with Windows Explorer, you will see a variety of file formats. Here's a list of the file types used by PatternMaker:

.PAT

This is the standard PatternMaker format.

.DXF

This is sometimes called the AutoCAD format. It is used by many popular CAD and graphics

programs.

.GRD

This is a saved grading file (Grading or Marker Studio only)

.KEY

This is a file containing a custom Hot Key configuration set.

.MAC

This file extension is used for the PatternMaker pre-designed garments (macros). See [Using the pre-designed garments](#)⁴⁰.

.MIF

This is a "macro information file," created by the Macro Project Editor (Home Studio and higher only)

.MMT

This is the "Master Measurement Table" set up by the designer of a macro. It is a template file that shows which body measurements the designer uses in drafting his/her macros.

.MTB

This is the personal measurement table that you save with your own name and measurements. Each .MTB file is based on an .MMT file from a particular designer.

Library Files

PatternMaker also lets you use a drawing file (.PAT) as a library of items that you can put into your patterns. You can load single objects, groups of objects, or symbols from a library file. Use a library whenever you want to insert many copies of the same item in many different drawings. Any drawing file can also be used as a library file. The library commands are found in the Symbols menu and are described in Using symbols & libraries.

One library of common pattern symbols is included with PatternMaker. If you have the Grading Studio or Marker Studio, you can also create your own libraries.

5.4 Advanced Snap modes

Together with Snap to Endpoint and Snap to Grid, these other Snap modes that will make your work much easier:

Name:

Hot Key:

What It Does:

Why You Would Use It:

Snap To Nearest

<CTRL>+<F4>

The cursor jumps to the contour of an object.

Useful if you need to select one object when you have several close together or overlapping. Also used if you need to draw a line exactly to the edge of an object.

Name:

Hot Key:

What It Does:

Why You Would Use It:

Snap Orthogonal

<CTRL>+<F5>

The cursor moves exactly horizontally or vertically.

When you want to move or draw something directly horizontal or vertical -- ie. lengthening or shortening something, etc.

Name: **Snap To Midpoint**
Hot Key: <CTRL>+<F6>
What It Does: The cursor jumps to the center between two consecutive vertices.
Why You Would Use It: When you need to find the middle of a line segment.

Name: **Snap To Intersection**
Hot Key: <CTRL>+<F7>
What It Does: The cursor jumps to a location where two line segments meet. There does not have to be a vertex at this location.
Why You Would Use It: If you need to draw or move something to the intersection of two other segments.

Name: **Snap To Offset**
Hot Key: <CTRL>+<F8>
What It Does: The cursor jumps to a location a specified distance horizontally and/or vertically from an existing vertex. Frequently, this is not along the contour of an object but "out in space" somewhere near the object.
Why You Would Use It: To find a specific distance away from an existing vertex.

Name: **Snap To Measured Distance**
Hot Key: <CTRL>+<F9>
What It Does: The cursor jumps to jumps along the contour of an object a specified distance away from an existing vertex.
Why You Would Use It: Often used with [ADD VERTEX](#)^[129] to place a new point in a specific location.

See also:
[Basic Snap modes](#)^[32]

Section



VI

Reference: Menu Commands

6.1 File Menu Commands

The **File** menu contains all the commands related to working with files, including Opening, Saving, and Printing. The commands you see will depend on what version of PatternMaker you are using. Not all commands are available in all versions.

NEW command


The NEW command starts a new drawing. The old drawing will be closed. If you have made changes to the drawing on the screen, you will be given a chance to save your work.

OPEN command

The OPEN command opens an existing drawing (a **.PAT** file) which has been saved on disk. Opening a new file replaces whatever is on the screen. If there is a drawing open, the program will ask you if it should be saved.

Procedure:

1. Click the Open icon, or select "Open" from the **File** menu. The **File** LaunchPad opens.
2. The LaunchPad interface automatically saves files in a designated location. If you saved your file in a different place, click the "Show Explorer Tree" checkbox and navigate to the correct location.
3. Select the file you want to open.
4. Click the "Open" button.



See also:

[Folders and file organization](#)^[12]

[DXF Import/Export](#)

[OPEN \(non-LaunchPad\) command](#)^[162]

MERGE command

The MERGE command adds one drawing to another. This is exactly the same as the OPEN command, except that the old drawing is not closed before loading the new one.

Procedure:

1. Select "Merge" from the **File** menu. The Open File dialog box appears.
2. Select the file you want to merge. Everything in this file will be added to the current drawing.
3. Click the "Open" button.

The [LAYER](#)^[141] settings will be changed to those of the new file. Any symbol definitions with duplicate names will be redefined.

MERGE *cannot* be reversed with the UNDO command.


Note: You cannot control where on the screen the new drawing will appear. Therefore, you may need to [MOVE](#)^[118] some pieces out of the way before using MERGE to avoid having pieces in the new file overlap the existing pieces.

See also:

[OPEN command](#)^[106]

SAVE command

The SAVE command saves the current drawing in a **.PAT** file. (To save in a different format, use [SAVE AS](#)^[108].) If the file you are working on already has a name, this file will be updated. If you have not named the file, the program will ask you for a name.



Pattern files have names that end in **.PAT**. A pattern file can be opened again later and modified and/or printed.

If the file already exists, a backup file will be made. Its file name extension will be **".BAK"**.

See also:

DXF Import/Export


SAVE AS command

The SAVE AS command saves the current drawing with a new file name, while leaving the current file unchanged. Use this to save your new work without erasing your old work.

Procedure:

1. Select "Save As" from the **File** menu. The **Save** LaunchPad opens.
2. The LaunchPad interface automatically saves files in a designated location. If you need to save your file in a different place, click the "Show Explorer Tree" checkbox and navigate to the new location.
3. Type a description for your file. This can be anything you want -- the type of garment, the style options you used, who the pattern is for, etc. This description is optional, but it is very useful when you want to locate the file later.
4. Type a name for your file, or select a file from the list. If the filename you select or type already exists, that file will be overwritten. If you type a new name, a new file is created.
5. PatternMaker automatically adds the **".PAT"** extension. If you want to save in a different format, for example **.DXF**, click the "Files of type" drop-down box, and select the file

- type from the list.
- Click the "Save" button.



See also:

[Folders and file organization](#)^[12]

[SAVE command](#)^[107]

DXF Import/Export

PRINT command

The PRINT command prints the entire drawing. If your printer is not big enough for the whole pattern, PatternMaker automatically prints as many pages as necessary. PatternMaker will print to any Windows-compatible printing device.

When you click the Print icon, or select "Print" from the **File** menu, the Print Preview window opens (see illustration below). This window lets you see how the drawing will be arranged on the pages.

The small boxes scattered over the drawing indicate the alignment marks on the corners of each page, showing you how many sheets of paper will be needed. These marks represent the printable area of the paper, according to the abilities of your printer. You can change from Portrait to Landscape mode (in File/Print Setup) and the marks will change accordingly.

The Print Preview menus are as follows:

Print:

Print Pages

Print the drawing according to the selected options

Print Setup	Open the Print Setup window to change printer options
Exit Printing	Close the Print Preview window and return to the drawing screen

Settings:

Alignment Marks	Choose whether you want the pages to print with alignment marks. The default is Yes.
Label Pages	Choose whether you want the pages to print with labels (Row/Column and Filename). The default is Yes.

Alignment:

Top/Middle/Bottom	Select how the printing is aligned on the pages up-and-down. The default is Top.
Left/Center/Right	Select how the printing is aligned on the pages side-to-side. The default is Left.

Zoom:

Zoom In (F2)	Make the view of the drawing larger
Zoom Out (F1)	Make the view of the drawing smaller

Note: Printing a pattern may take lots of pages on a desktop printer, and require taping a lot of pages together. To avoid wasting paper, make sure your pattern has only the pieces you need and that they are as close together as possible. Use the [MOVE](#)^[118], [ROTATE](#)^[122] and [ERASE](#)^[125] to arrange the pieces for printing.

Note: If you are using a macro, remember that you might need to leave room around the edges of the pieces to cut the seam allowances. Seam allowances are not always included on macro pattern pieces automatically. If you want to print the pattern with seam allowances and they are not included, use the [OFFSET](#)^[115] or [SEAM ALLOWANCE](#)^[116] commands before printing.

See also:

[PRINT SELECT command](#)^[110]
[PRINT REGION command](#)^[111]
[PRINT SETUP command](#)^[111]
[Assembling Printed Pages](#)^[62]

PRINT SELECT command

The PRINT SELECT command lets you choose one or more objects to print, rather than the entire drawing.

Procedure:

1. Select the PRINT SELECT command from the **File** menu. The prompt on the command line says: Select Objects to Print:
2. Click **LM** on one or more objects. Each piece that you select is highlighted. If you make a mistake, click on an object again to un-select it.
3. **To stop selecting objects**, click **RM**, or press the <ESC> key.
4. The Print Preview window will now open. Continue according to the [PRINT](#)^[109] instructions. The program will print as many pages as necessary to cover the object(s) you selected.

See also:

[PRINT REGION command](#)^[111]
[Assembling Printed Pages](#)^[62]

PRINT REGION command

The PRINT REGION command lets you select a rectangular area to print, rather than the entire drawing. All objects (or portions of objects) within the selected area will be printed.

Procedure:

1. Select the PRINT REGION command from the **File** menu. The prompt on the command line says Enter a point, <ESC> to cancel
2. Click **LM** on one corner of the area you wish to print -- for example, the upper left corner.
3. The prompt on the command line says Second point, <ESC> to cancel. As you move the mouse around, you will see the box changing shape. This box represents the area that will be printed.
4. When you have defined the area you want to print, click **LM** again. The Print Preview window will now open. Continue according to the [PRINT](#)^[109] instructions. The program will print as many pages as necessary to cover the area you selected

See also:

[PRINT SELECT command](#)^[110]
[Assembling Printed Pages](#)^[62]

PRINT SETUP command

The PRINT SETUP command takes you to the Windows Print Setup dialog box. Here you can change which printer you are going to use, and also change the page orientation (Portrait to Landscape, or vice versa).

You can access this dialog box either from the **File** menu in the main drawing screen, or from the Print menu in the Print Preview window.

Make the changes you want, and then click the "OK" button.


MACRO command

The MACRO command runs a macro. Macros are small programs that run inside PatternMaker to create basic blocks or complete patterns.


Before you run a macro, set up a personal [measurement table](#)^[144]

Procedure:

1. Click on the Macro icon, or select "Macro" from the **File** menu.
2. The **Macro** LaunchPad opens. Select the designer, collection, and garment file that you want. The descriptions and focus pictures help you make your selection.




3. Select the macro you want to run and click the "OK" button. It may take a few seconds for PatternMaker to load the macro.
4. You will now see a series of dialog boxes which ask questions and offer choices. The choices are different for each macro. (For instance, for the womens dress, you will be asked if you want a sleeveless dress or one with sleeves.) To continue through the macro, use your mouse to click on one of the options. If you click "Cancel," the macro will abort and you will be returned to the drawing screen.



5. After you have made your choices, it's time to enter your measurements. You can either use a saved [measurement table](#)^[144], or you can enter the measurements manually.

Using a Measurement Table


Select a measurement table and click the "Open" button. The measurements from this table will be "plugged into" the macro.



NOTE: The measurement tables are automatically filtered to show only the tables matching the designer whose macro you are running. If you don't see a table that you expect to see, make sure you've saved a measurement table for the correct designer.

Entering Measurements Manually

If you are not using a saved measurement table, click the "Cancel" button to bypass the dialog box. The macro will then display a dialog box into which you can enter your measurements manually.



Some macros may have two dialog boxes for measurements. Fill these in from your *measurement chart*. Remember to use decimal numbers, so 8-3/4 inches is 8.75 inches and so forth. (Use the Fraction Conversion Chart for help.) Be careful to enter the right numbers in the right spaces. When you are ready to continue, click the "OK" button.

- While the macro is running, the mouse pointer icon turns into an hourglass. You may have to wait for the macro to run, especially if you do not have a fast computer, or if the macro you are using is particularly complicated. You will know the macro is done when the hourglass cursor changes back to an arrow and the prompt Command : appears on the status bar.

IF YOU CANNOT SEE THE PATTERN PIECES, OR IF YOU ONLY SEE PART OF THEM, PRESS THE <END> KEY TO VIEW ALL THE PIECES IN THE DRAWING.

The macro will draw your new pattern in the drawing area. If there is a drawing on the screen when you run a macro, the macro will be *added* to what is on the screen. It may overlap existing

pattern pieces. If this happens you can use the [MOVE](#)^[118] command to move things around. Use the [ZOOM and PAN commands](#)^[137] to view different parts of the drawing.

A macro can be run as many times as you wish. You can reuse your own measurement table, or you can create new tables for many different people.

Once the macro has created the pattern on the screen, the drawing can be saved as a [.PAT](#) file, to be opened and printed again later. With the Deluxe Version or higher, you can also edit the .PAT file, but you cannot automatically change the body measurements used in the garment. To change the measurements, run the macro again.

See also:

[Set start locations](#)^[94]

EXIT command

The Exit command allows you to exit the PatternMaker program. If there is a drawing open, you will be given a chance to save it.

6.2 Draw Menu Commands

The **Draw** menu contains commands used to create various objects in your drawing. Everything in your drawing is an object – the outline of a bodice piece is an object, the arrow showing the grainline is an object, and the text that says "Bodice Front" is an object.

DIM command

This command draws dimension lines. Dimensions are one of the four kinds of objects in PatternMaker. A dimension object has two arrows indicating two points, and some numbers giving the distance between the points. If you ever change or resize a dimension object, its length is recalculated and the numbers are updated.

Procedure:

1. Click on the Dim icon, or select "Dim" from the **Draw** menu. The prompt on the command line says: Enter a point; <ESC> to cancel:.
2. Click on the screen or type a position in [coordinate format](#)^[34] to indicate the start point of the dimension line. This would usually be a point on one end of the line or object you want to measure. The prompt on the command line says: Second point; <ESC> to cancel:.
3. Click on the screen or type a position in coordinate format to indicate the end point of the dimension line (a point on the other end of the line or object). The prompt on the command line says: Location for label:
4. As you move the mouse around, you can see where the label will be placed. Click on the screen when the label is positioned where you want it. The text will be automatically inserted indicating the distance between the two points.

Note: It is often convenient to use Snap To End Point to place Dimension lines next to objects you want to measure. See [SNAP Commands](#)^[140] for more details.

Note: You can change the appearance of the DIM units, including the size of the text and the length of the arrows. See the [DIM SETTINGS](#)^[92] and [UNITS](#)^[76] commands for more details.

DIM is used for measuring between two points in a straight line. To measure along a curve, use SET/MEASURE DISTANCE.

LINE command

The LINE command draws a line. A line is a polygon object with two points. You can use the various editing commands to change a line, just like any other object.

Procedure:

1. Click the Line icon, or select "Line" from the **Draw** menu. The command name LINE will appear in **green** on the right side of the status bar. The prompt on the command line says Enter a point, <ESC> to cancel:
2. Enter the first point of the line by clicking **LM** or by typing a position in [coordinate format](#)^[34]. The prompt on the command line says Second point, <ESC> to cancel:
3. Enter the second point by clicking **LM** or by typing a position in coordinate format
4. You can tell when you are finished with the command when the command name LINE on the status bar returns to **purple**. To cancel the command without drawing the line, click **RM** or press <ESC> until the command name is purple.

See also:

[Setting drawing preferences](#)^[82]
CHANGE OBJECT command

OFFSET command

The OFFSET command creates a polygon object that is offset a certain distance from an existing polygon. This is useful for creating fixed-width seam allowances. You can offset both open and closed polygons, and you can put the offset on either the inside or the outside of the selected object(s).

Procedure:

1. Click on the Offset icon, or click "Offset" on the **Draw** menu. The command name OFFSET will appear in **green** on the right side of the status bar. The prompt on the command line says Select object to offset:
2. Click **LM** on the object you want to add seam allowance to. You can only select one object at a time. The command line will keep you informed as objects are selected and unselected.
3. **To stop selecting objects**, press the <ESC> key, or click **RM**. An "Offset Distance" dialog box will appear.
4. Enter the amount of seam allowance you want. Remember to use decimal numbers, not fractions. (See the Fraction Conversion Chart for help.) A positive number will draw the offset outside the original object; a negative number will put the offset object inside the original object.
5. Click the "OK" button. A seam allowance will be drawn around the selected piece.

The offset object, once drawn, is an object separate from the original object. You can do any of the things with it that you can do with any other PatternMaker drawing object.

NOTE: The OFFSET command may not work well for objects that contain sharp angles or inward bends, or that overlap or cross over themselves. Most normal pattern pieces will not have this problem unless they contain darts. One way to avoid this problem is to draw the dart as a separate object from the main pattern piece. Also try the [OFFSET LINES command](#)^[93].

HINT: Use ID POINT if you think your object may have "hidden" kinks or stray vertices.

See also:

[SEAM ALLOWANCE command](#)^[116]
CHANGE OBJECT command

SEAM ALLOWANCE command

The SEAM ALLOWANCE command adds a seam allowance to an object. You can vary the width of the seam allowance as it goes around the object. You can add seam allowances to both open and closed polygons, and you can put the seam allowance on either the inside or the outside of the selected object(s).

Procedure:

1. Click "Seam Allowance" on the **Draw** menu. The prompt on the command line says `Select offset starting point:`.
2. Click **LM** on the vertex of a polygon object where you want the seam allowance to begin. If you make a mistake, just click another point to replace the first. The command line keeps you informed as points are selected and unselected.
3. **When you have selected the point you want to start with**, click **RM** or press <ESC>. The prompt on the command line says `Select end of segment:`.
4. Click **LM** on a second point of the same object and then click **RM** (or press <ESC>) again. These two points define the segment to which the seam allowance will be added. PatternMaker highlights the section connecting these two points and asks you if it is the right section. (The program needs to know whether to go clockwise or counterclockwise around the object.) If you click "Yes" the command will continue; if you click "No" the program will highlight the section of the object in the opposite direction and repeat the question.
5. Next, a dialog box appears, asking you for the offset distance. Enter the width of the seam allowance for this section. A positive number will draw the offset outside the original object; a negative number will draw the offset inside the original object. Remember to use decimal numbers, not fractions (see the Fraction Conversion Table).
6. To exit the dialog box, choose one of the three option buttons:
 - Continue:** the seam allowance is added to the selected segment. Click the "OK" button to return to the drawing screen to select the next segment. Steps 4 and 5 will be repeated until you select one of the "Done" options, or go all the way around the original object.
 - Done/Closed:** the seam allowance is made into a closed object -- in other words, it continues all the way around the original object at the width you specified
 - Done/Open:** the seam allowance ends just as it is (an open object)
7. Click the "OK" button to accept the settings and return to the drawing screen to select the next segment; click "Cancel" to abort the command.

After the seam allowance is drawn, you can use the CHANGE OBJECT command to change the line style of one of the objects. This can be useful, for example, if you want to indicate a stitching line by using a dashed or dotted line.

The seam allowance object, once drawn, is an object separate from the original object. You can do any of the things with it that you can do with any other PatternMaker drawing object.

NOTE: The SEAM ALLOWANCE command may not work well for objects that contain sharp angles or inward bends, or that overlap or cross over themselves. Most normal pattern pieces will not have this problem unless they contain darts. One way to avoid this problem is to draw the dart as a separate object from the main pattern piece.

HINT: Use ID POINT if you think your object may have "hidden" kinks or stray vertices.

See also:

[OFFSET command](#)¹¹⁵
[SNAP TO OFFSET](#)¹⁴⁰

6.3 Edit Menu Commands

PatternMaker has many editing commands that allow you to move, change and adjust objects. These commands are all found in the **Edit** menu.

One thing these commands all have in common is that when you select an object, the command applies to the entire object. There is a second set of commands which have to do with points of objects. These are listed in the **Point** menu.

UNDO command

The UNDO command reverses the last editing or drawing command.

Procedure:

1. Click the Undo icon, select "Undo" from the **Edit** menu, or type <CTRL>+Z.
2. The last change you made will be undone. If you drew a new object, it will be erased. If you moved an object, it will be returned to its original position, and so on.

Some commands cannot be undone, including: SAVE, Close, SAVE AS, and Create Symbol. ZOOM and PAN commands don't count--UNDO will undo whatever you did before the Zoom. In general, drawing, editing, grading and marker commands can be undone.



PatternMaker now supports a multiple-undo/redo feature. The number of commands you can undo or redo is determined by the configuration settings you have selected (see [Configure Options](#)⁸²). This number is limited only by the speed and memory capacity of your computer -- a longer Undo history will make your computer run more slowly.

If you undo the maximum number of steps, the command is inactive until you complete another undoable action.

See also:

[REDO command](#)¹¹⁸

REDO command



The REDO command restores the last editing or drawing action that was reversed with the UNDO command.

Procedure:

1. Click the Redo icon, or select "Redo" from the **Edit** menu.
2. The last action you undid will be redone.

See also:

[UNDO command](#)^[117]

MOVE command

The MOVE command moves one or more objects.

Procedure:

1. Click on the Move icon, or select "Move" from the **Edit** menu. The command name MOVE will appear in **green** on the right side of the status bar. The prompt on the command line says Select object, ? for help, <ESC> = done.
2. Click **LM** on the object(s) to move. You can select and unselect as many objects as you want by repetitive clicking. The command line will keep you informed as objects are selected and unselected. If you want to move a whole pattern piece, be sure to select *all* of its pieces – i.e. darts in a bodice piece, grainline marks, etc.
3. **To stop selecting objects**, press the <ESC> key, or click **RM**. The prompt on the command line says Base point?
4. The base point (the start of the move) is like grabbing a handle on the pieces to move. Simply click **LM** somewhere within the selected object(s). The command line will now ask for Destination?
5. Move the mouse around to move the piece(s), or enter a destination by typing a position in [coordinate format](#)^[34]. You will see a **light blue line** showing the origin and destination of the piece(s).

Note: Do not "click and drag." Click once where you want to start moving the pieces; release the mouse button; and then click again where you want them to end up.

6. When the pieces reach the desired location, click **LM** to release them.

If you want to move pieces off the edge of the screen, use the ZOOM or PAN functions to see where you are going. You can use ZOOM and/or PAN even if you're in the middle of another command.

See also :

[COPY command](#)^[119]

COPY command

The COPY command copies one or more objects. COPY is just like MOVE, except that you get one copy of the selected objects in the original position, and one copy in the new position.

Procedure:


1. Click the Copy icon, or select "Copy" from the **Edit** menu. The command name COPY will appear in **green** on the right side of the status bar. The prompt on the command line says Select object, ? for help, <ESC> = done.
2. Click **LM** on the object(s) to copy. You can select and unselect as many objects as you want by repetitive clicking. The command line will keep you informed as objects are selected and unselected. If you want to copy a whole pattern piece, be sure to select *all* of its pieces – i.e. darts in a bodice piece, grainline marks, etc.
3. **To stop selecting objects**, press the <ESC> key, or click **RM**. The prompt on the command line says Base point?
4. The "base point" is like grabbing a handle on the pieces to move. Simply click somewhere within the selected object(s). The command line will now ask for Destination?
5. Move the mouse around to copy the piece(s), or enter a destination by typing a position in [coordinate format](#)^[34].. You will see a **light blue line** showing the origin and destination of the piece(s).
6. When the pieces reach the desired location, click **LM** to release them.


See also:

[MOVE command](#)^[118]

MIRROR command

The MIRROR command creates a mirror image copy of the selected object(s), leaving the original object in place.





Procedure:

1. Select "Mirror" from the **Edit** menu. The command name MIRROR will appear in **green** on the right side of the status bar. The prompt on the command line says Select object, ? for help, <ESC> = done.
2. Click **LM** on the object(s) you want to mirror. You can select and unselect as many objects as you want by repetitive clicking. The command line will keep you informed as pieces are selected and unselected. If you want to mirror a whole pattern piece, be sure to select *all* of its pieces -- ie. darts in a bodice piece, grainline marks, etc.
3. **To stop selecting objects**, press the <ESC> key, or click **RM**. The prompt on the command line says Start of line to reflect across:.
4. Click on the screen to indicate the beginning of the reflection line. The prompt on the command line says Second point of reflection line:
5. If you want a perfectly vertical mirror, just press <ENTER>. Otherwise, move the mouse around, and watch the reflection line move accordingly. You can reflect at any angle.
6. When you have the line the way you want it, click **LM**. The object(s) will be mirrored across the line.

The MIRROR command is important for completing the second half of a pattern. For instance, you can draft the right side of a blouse in great detail, then make the left side all at once with MIRROR.

Example: Suppose your blouse pattern has a single-piece front. Make a half front piece – one that goes from the Center Front line to the right side seam. Add darts, seam allowances, adjust the fit, etc. When it's all ready, select the MIRROR command. Select the main piece as well as the darts and other objects. When you are prompted for the mirror line, use Snap To Endpoint (<CTRL>+<F3>) to select the Center Front-Collar point and the Center Front-Waist point. Now you have two pieces that meet along the Center Front line. Use [JOIN](#)^[128] to join these pieces together, and you have your symmetrical front piece.


See also:

[REFLECT command](#)^[121]
[FLIP HORIZ command](#)^[126]
[FLIP VERT command](#)^[127]

REFLECT command



The REFLECT command reflects an object across a line that you draw. This line can be drawn at any angle.



Procedure:

1. Click the Reflect icon, or select "Reflect" from the **Edit** menu. The command name REFLECT will appear in **green** on the right side of the status bar. The prompt on the command line says Select object, ? for help, <ESC> = done.
2. Click **LM** on the object(s) you want to reflect. You can select and unselect as many objects as you want by repetitive clicking. The command line will keep you informed as pieces are selected and unselected. If you want to reflect a whole pattern piece, be sure to select *all* of its pieces -- ie. darts in a bodice piece, grainline marks, etc.
3. **To stop selecting objects**, press the <ESC> key, or click **RM**. The prompt on the command line says Start of line to reflect across:.
4. Click on the screen to indicate the beginning of the reflection line. The prompt on the command line says Second point of reflection line:
5. If you want a perfectly vertical reflection, just press <ENTER>. Otherwise, move the mouse around, and watch the reflection line move accordingly. You can reflect at any angle.

6. When you have the line the way you want it, click **LM**. The object(s) will be reflected across the line.

See also:

[MIRROR command](#)¹¹⁹

[FLIP HORIZ command](#)¹²⁶

[FLIP VERT command](#)¹²⁷

ROTATE command

The ROTATE command rotates one or more objects around a "center point".

Procedure:

1. Click the Rotate icon, or select "Rotate" from the **Edit** menu. The command name ROTATE will appear in **green** on the right side of the status bar. The prompt on the command line says Select object, ? for help, <ESC> = done.
2. Click **LM** on the object(s) to rotate. You can select and unselect as many objects as you want by repetitive clicking. The command line will keep you informed as objects are selected and unselected. If you want to rotate a whole pattern piece, be sure to select *all* of its pieces – i.e. darts in a bodice piece, grainline in a sleeve, etc.
3. **To stop selecting objects**, click **RM**, or press the <ESC> key. The prompt on the command line says Rotate about what point?
4. Click on the point you want the pieces to rotate around – like the center of a clock. The prompt on the command line says Rotation (angle or base point of rotation):
5. You can enter the rotation angle in one of three ways:

- *Angle:* Type in the number of degrees you want to rotate the object(s). Your objects will rotate counterclockwise (left) that many degrees. To rotate the objects 90 degrees, type 90 and press <ENTER>. To go 90 degrees clockwise (right), type 270 and press <ENTER>. (There's no cursor on the command line, and you don't have to click there -- just type the numbers.) After you press <ENTER>, the pieces rotate, and you are done with the command.
- *Base point and end point:* The base point is like a "handle" that you use to pick up the object(s). Click somewhere to indicate the base point. Next, move the mouse around and watch the object(s) rotate around the center point. As you do this, you will see two cyan (bluish) lines which indicate the angle of rotation between the two points. When the object has rotated as much as you want, click **LM** to end the rotation and "drop" the objects(s).

Hint: Using Snap To Endpoint or Snap To Grid when you select the start and end points will allow you to rotate objects to align with each other, or with a horizontal or vertical line.

- *Base point and distance:* Click somewhere to indicate the base point, then type a number. The number represents either inches or centimeters, depending on the Units you are working in. PatternMaker calculates a rotation angle such that the selected point moves the specified distance. This is for certain pattern layout procedures that require you to rotate an object for a measured distance.

You don't have to select the above choices from a list. Just start entering the information and


PatternMaker will figure out which method you are using.

See also:

[ROTATE VERTEX command](#) ¹³¹

SCALE command

The SCALE function makes objects proportionally larger or smaller, using one scaling factor for both X (horizontal) and Y (vertical) directions. Use this command to change the size of an object without changing its shape. All four types of PatternMaker objects can be changed with the SCALE command.



Procedure:

1. Select "Scale" from the **Edit** menu. The command name SCALE will appear in **green** on the right side of the status bar. The prompt on the command line says **Select object, ? for help, <ESC> = done.**
2. Click **LM** on the object(s) to scale. You can select and unselect as many objects as you want by repetitive clicking. The command line will keep you informed as objects are selected and unselected. If you want to scale a whole pattern piece, be sure to select *all* of its pieces – i.e. darts in a bodice piece, grainline marks, etc.
3. **To stop selecting objects**, click **RM**, or press the <ESC> key.
4. The command line will now display the original dimensions of the object(s). A cyan (bluish) square is drawn to indicate the original area of the selected object(s). As you move the mouse, a green box indicates the new area.
5. Click **LM** when the green box is the size you want the objects, or use one of the following options. Select an option either by typing a letter, or with an icon:

C = set center

By default, the lower left corner of the cyan square is the center of expansion, i.e. it doesn't move. If you want to have a different center, type C. You will be prompted for a new center point. Input this point and then continue with the command.

P = scale around corner

This option sets the lower left corner as the center of expansion. It is the opposite of the C option. This is the default for the command.

F = enter scaling factor

You will be asked for the scaling factor. (For example, ".5" is half the size; "3" is three times the size.) Enter this in the dialog box and select "OK". This option will also be selected if you type in a single number.

X/Y = size to measure

These options calculate a scaling factor to give you a measurement you want. This will save you doing some math. You will be asked to select two points in the drawing. (To measure horizontally, select X; to measure vertically,

select Y.) PatternMaker will tell you the current distance between these points, and ask you what you want the distance to be. PatternMaker will then calculate a scaling factor to give you the distance you want.


Example: Suppose you have used your digitizing tablet to copy a pattern from a book in 1/6 scale. Choose the **SCALE** command, select all objects, then type F and enter a scaling factor of 6. When you print the pattern, it will be life-sized.

See also:

[RESIZE command](#)^[124]

RESIZE command

The RESIZE command is used to change an object's shape *and* size. Different scaling factors are used for the X (horizontal) and Y (vertical) directions, so you can change the size and proportion of objects simultaneously. Only POLY and [DIM](#)^[114] objects can be changed with the RESIZE command.



Procedure:

1. Click the Resize icon, or select "Resize" from the **Edit** menu. The command name RESIZE will appear in **green** on the right side of the status bar. The prompt on the command line says Select object, ? for help, <ESC> = done.
2. Click **LM** on the object(s) to resize. You can select and unselect as many objects as you want by repetitive clicking. The command line will keep you informed as objects are selected and unselected. If you want to resize a whole pattern piece, be sure to select all of its pieces -- ie. darts in a bodice piece, grainline marks, etc.
3. **To stop selecting objects**, click **LM**, or press the <ESC> key.
4. The command line will now display the original dimensions of the object(s). A **cyan** (bluish) square is drawn to indicate the original area of the selected objects. As you move the mouse, a green box indicates the new shape and size. The objects will be resized by X and Y factors that make them fit the green box.
5. When the green box is the size and shape you want, you can click **LM** to resize the object(s). However, rather than using the mouse to resize "by eye," you will usually want to use one or more of the following options. Select an option either by typing a letter, or with an icon:

C = set center

By default, the lower left corner of the cyan square is the center of expansion, i.e. it doesn't move. If you want to have a different center, for example if you want the right side of an object to stay put while the left side moves, type C. You will be prompted for a new center point. Input this point and then continue with the command.

<i>P = resize around corner</i>	This option sets the lower left corner as the center of expansion. It is the opposite of the C option. This is the default for the command.
<i>F = enter scaling factor</i>	You will be asked for the scaling factors. (For example, ".5" is half the size; "3" is three times the size.) Enter them in the dialog box and click "OK." If one of the numbers is negative, the selected object(s) will be reversed. <i>Example: Suppose your material requires a shrinkage allowance of 3% in one direction and 6% in the other. Your pattern pieces need to be expanded by factors of 1.03 and 1.06, respectively. After selecting all objects in the drawing, type F. Type 1.03 and 1.06 into the dialog box and select "OK".</i>
<i>X/Y = size to measure</i>	These options calculate a scaling factor to give you a measurement you want. This will save you doing some math. If you select X, the objects will be resized in the X direction, but the Y scale will stay the same. If you select Y, the Y scale will change, and the X scale stays the same. You will be asked to select two points in the drawing. PatternMaker will tell you the current distance between these points, and ask you what you want the distance to be. PatternMaker will calculate a scaling factor to give you the distance you want. <i>Example: Suppose you have a blouse with a center front measurement of 14 inches and you want to change it to 15 inches. Select the blouse object and any associated objects such as darts, etc. Then type Y. The prompt will ask you for the first control point and then the second control point. Use Snap to End Point to select the points at the top and bottom of the center front line. A dialog box will then say,</i> Original measurement is 14.000000 Type in 15 and click "OK." Your blouse will be made taller but its width will stay the same.

See also:
[SCALE command](#)  123

ERASE command

The ERASE command erases one or more objects.

Procedure:

1. Click on the Erase icon, or click "Erase" on the **Edit** menu. The command name ERASE will appear in **green** on the right side of the status bar. The prompt on the command line says Select object, ? for help, <ESC> = done.
2. Click **LM** on the object(s) to erase. As you click on objects, they will be highlighted. If you select something by accident, just click on it again to un-highlight it. You can select and unselect as many objects as you want by repetitive clicking.


3. **To stop selecting objects**, click **RM**, or press the <ESC> key. The object(s) you selected will be erased.

Note: *Although you can abort many commands by pressing the <ESC> key, the **ERASE** command cannot be aborted.* If you press the <ESC> key while an object is highlighted, it will be erased. If you want to cancel the command, either un-select all objects and then press <ESC>, or go ahead and finish the command and then immediately use the [UNDO command](#)¹¹⁷ before doing anything else.

FLIP HORIZ



The FLIP HORIZONTAL command alters an object by "spinning" it within the outline of its current location. This command does not move or copy the object to a different part of the screen. The selected piece moves horizontally within its space (around a vertical axis).



Procedure:

1. Click the Flip Horizontal icon, or select "Flip Horiz" from the **Edit** menu. The command name FLIPHORIZ will appear in **green** on the right side of the status bar. The prompt on the command line says Select object, ? for help, <ESC> = done.
2. Click **LM** on the object(s) you want to flip. You can select and unselect as many objects as you want by repetitive clicking. The command line will keep you informed as pieces are selected and unselected.
3. **To stop selecting objects**, press the <ESC> key, or click **RM**. The piece(s) will be immediately flipped.


See also:

[MIRROR command](#)¹¹⁹
[REFLECT command](#)¹²¹
[FLIP VERT command](#)¹²⁷

FLIP VERT



The FLIP VERTICAL command alters an object by "spinning" it within the outline of its current location. This command does not move or copy the object to a different part of the screen. The selected piece moves vertically within its space (around a horizontal axis).



Procedure:

1. Click the Flip Vertical icon, or select "Flip Vert" from the **Edit** menu. The command name FLIPVERT will appear in **green** on the right side of the status bar. The prompt on the command line says Select object, ? for help, <ESC> = done.
2. Click **LM** on the object(s) you want to flip. You can select and unselect as many objects as you want by repetitive clicking. The command line will keep you informed as pieces are selected and unselected.
3. **To stop selecting objects**, press the <ESC> key, or click **RM**. The piece(s) will be immediately flipped.

See also:

[MIRROR command](#)¹¹⁹
[REFLECT command](#)¹²¹
[FLIP HORIZ command](#)¹²⁶

CUT command

The CUT command cuts one object along a line defined by a second object. The CUT command works with open or closed polygon objects. It does not work with text, dimension lines, or symbols.

Remember: This CUT command has nothing to do with the "cut and paste" features found in many Windows programs.

Procedure:

1. In order to use the CUT command, you must already have in your drawing the object you want to cut, and the object you will cut with (such as a line). You may need to move an existing object, or draw a completely new object. Do this first, before continuing with this

command.

Hint: Sometimes you will cut an object with a pre-existing object. More often, you will draw a new object to serve as the cutting line. Do the cut, then use ERASE to get rid of the cutting line and the piece(s) you don't want.

2. When you are ready to cut, click on the Cut icon, or select "Cut" from the **Edit** menu. The command name CUT will appear in **green** on the right side of the status bar. The prompt on the command line will say: Select object to cut:
3. Click **LM** on the object you want to cut. In the CUT function you can only select one object at a time, so if you click on a second object, it will replace the first as the object that is highlighted.
4. **When you have the correct object selected**, click **RM**, or press the <ESC> key. The prompt on the command line will say: Select object to cut with:
5. Click **LM** on the object that will form the cutting line. This is like a cookie cutter, or like the line the scissors follow when cutting the first object.
6. After you select the second object, click **RM** or press the <ESC> key. The first object will be cut by the second. Nothing will appear to have changed in the drawing, because the objects do not move. However, if you apply a command such as MOVE or ERASE on one of the pieces, you will notice the cut objects.

If you're sure nothing happened, it may be because you selected objects that don't overlap. Use [MOVE](#)^[118], [MOVE VERTEX](#)^[130] or [ADD VERTEX](#)^[129] to give your objects some overlap.

Note on CUT and JOIN: *Unlike many CAD programs, PatternMaker thinks of objects as shapes with an inside and an outside. Therefore, if you try to use CUT or JOIN on objects that overlap themselves, or cross over themselves, PatternMaker may be confused because it doesn't know which is inside and which is outside. If you get a strange result, use the UNDO command. Then use ID POINT to see where the vertices of your objects really are. You can fix them with the MOVE VERTEX command.*

If you cut apart an object containing grading arrows, PatternMaker may add arrows to the pieces so they will still grade the same.

See also:

QUICK CUT command

[JOIN command](#)^[128]

JOIN command

The JOIN command merges two overlapping polygon objects together into one object. With closed objects, this is like taping two pieces of paper together. With open objects, it joins them end-to-end. The combined object will have the color and fill style of the first chosen object.

The JOIN command is designed for use with polygon objects. It does not work with text or symbols.

Procedure:

1. Click the Join icon, or select "Join" from the **Edit** menu. The command name JOIN appears in **green** on the right side of the status bar, and the prompt on the command line says Select first object to join:
2. Click **LM** on one polygon object. Only one object can be selected at a time, so if you

click on a second object, the first object will be unselected.

3. **To stop selecting objects**, click **RM**, or press the <ESC> key. The prompt **Select second object to join:** will now appear on the command line.
4. Select the second object that you wish to join to the first. It must overlap, or at least touch, the first object.
5. When you have selected the second object, press the <ESC> key, or click **RM**. The two objects will be joined.

Note on CUT and JOIN: *Unlike many CAD programs, PatternMaker thinks of objects as shapes with an inside and an outside. Therefore, if you try to use CUT or JOIN on objects that overlap themselves, or cross over themselves, PatternMaker may be confused because it doesn't know which is inside and which is outside. If you get a strange result, use the UNDO command. Then use ID POINT to see where the vertices of your objects really are. You can fix them with the MOVE VERTEX command.*

See also:

[CUT command](#)^[127]

6.4 Point Menu Commands

The **Point** menu contains editing commands that are used to move or modify points (vertices). These are different than the commands in the **Edit** menu because they apply only to vertices – you can change some of the vertices of an object and leave the rest unchanged.

Commands in the Point menu apply mostly to Polygon objects, but some, such as MOVE VERTEX, can be used on points in any object type.

ADD VERTEX command

The ADD VERTEX command adds another vertex (point) to any polygon object. It does not work with text, dimensions or symbol insertions.

Procedure:

1. Select "Add Vertex" from the **Point** menu. The command name ADD VERTEX will appear in **green** on the right side of the status bar. The prompt on the command line says **Select object to add vertex to:**
2. Click **LM** on one segment of an object. The selected segment will turn red. If you click on the wrong segment, just click again on the correct one.
3. When you have selected the segment you want, click **RM**, or press the <ESC> key. The prompt on the command line says **Location for new vertex:**
4. Click on the segment to show the position for the new point.

Tip: Try using various [snap modes](#)^[140] to help in placing the new point. Use Snap To Nearest or Snap To Measured Distance if you want the new point to lie on an existing line or arc of the object; use Snap To Midpoint to place a point exactly halfway between two others.

See also:

[DELETE VERTEX command](#)^[130]
[MOVE VERTEX command](#)^[130]
[CORNER VERTEX command](#)^[133]
[ROUND VERTEX command](#)^[133]

DELETE VERTEX command

The DELETE VERTEX command removes vertices (points) from an object(s). If the object has only one vertex, the object will be deleted.

Procedure:

1. Select "Delete Vertex" from the **Point** menu. The command name DELETE VERTEX will appear in **green** on the right side of the status bar. The prompt on the command line says Select point, ? for help, <ESC> = done.
2. Click **LM** on the point(s) you want to delete. You can select and unselect as many points as you want by repetitive clicking. They don't all have to be on the same object. Points will turn **red** as they are selected. If you accidentally click on the wrong point, just click on it again to unselect it.
3. **To stop selecting points**, press <ESC> or click **RM**. The selected point(s) will be deleted.

See also:

[ADD VERTEX command](#)^[129]

MOVE VERTEX command

The MOVE VERTEX command moves one or more points of your objects.

Procedure:

1. Select "Move Vertex" from the **Point** menu. The prompt on the command line says Select point(s), ? for help, <esc>=done:
2. Click **LM** on the point(s) you want to move. Points will turn **red** as they are selected. If you accidentally click on the wrong point, just click on it again to unselect it.
3. **To stop selecting points**, click **RM**, or press the <ESC> key. The prompt on the command line will say Base point?
4. The base point is like the "handle" you will use to pick up and move the points. Click **LM** somewhere near the selected point(s) to indicate the base point. The prompt changes to Destination:
5. As you move the mouse around, you will see the selected points moving, also. Click **LM** to "drop" the point(s) at the destination, or click **RM** to cancel the command.

***Tip:** You can use coordinates to move the points with more accuracy than you can achieve with the mouse. See [Using Coordinates](#)^[34] for more details.*

See also:

[ADD VERTEX command](#)^[129]
[DELETE VERTEX command](#)^[130]
[CORNER VERTEX command](#)^[133]

[ROUND VERTEX command](#)¹³³

ROTATE VERTEX command

The ROTATE VERTEX command rotates one or more points around a "center point". You can use ROTATE VERTEX to rotate some of the points in an object while leaving the rest where they are. This is especially useful for rotating darts.

Procedure:

1. Select "Rotate Vertex" from the **Point** menu.
2. Click **LM** on the point(s) you want to rotate. Points will turn **red** as they are selected. If you accidentally click on the wrong point, just click on it again to unselect it.
3. **To stop selecting points**, click **RM**, or press the <ESC> key. The prompt on the command line says `Rotate about what point?`
4. Click **LM** on a point the others will be rotated around. The prompt on the command line will say `Rotation (angle or base of rotation):`
5. You can enter the rotation angle in one of three ways:
 - *Angle:* Type in the number of degrees you want to rotate the object(s). The selected points will rotate counterclockwise (left) that many degrees. To rotate the points 90 degrees, type 90 and press <ENTER>. To go 90 degrees clockwise (right), type 270 and press <ENTER>. (There's no cursor on the command line, and you don't have to click there – just type the numbers.) After you press <ENTER>, the points rotate, and you are done with the command.
 - *Base point and end point:* Click to enter two points. The angle of rotation is the angle between the two points. Two **cyan (bluish)** lines appear to indicate the angle. After you click on the base point, you can watch the selected points move as you move the mouse around. Click **LM** to place the points in the new position and complete the command.
 - *Base point and distance:* Enter a point, then type in a number. PatternMaker calculates a rotation angle such that the selected point moves the specified distance. After you type the number and press <ENTER>, the points rotate, and you are done with the command.

You don't have to select the above choices from a list. Just start entering the information and PatternMaker will figure out which method you are using.

See also:

[ROTATE command](#)¹²²

DELETE SEGMENT command

The DELETE SEGMENT command will remove a line or arc segment from a polygon object. If it is a closed polygon, this will make it an open polygon. If it is already open, this will remove a segment from one end, or break it into two objects.

Procedure:

1. Select "Delete Segment" from the **Point** menu. The prompt on the command line will say `Select segment to delete:`

2. Click **LM** on a segment to remove. With this command you can only select one segment at a time, so if you click on a second segment, it replaces the first.
3. When you have selected the correct segment, press <ESC> or click **RM**. The selected segment will be removed.

See also:

CLOSE OBJECT command


DIVIDE SEGMENT command




Use DIVIDE SEGMENT to add evenly-spaced vertices to one segment of an object. This command will only work on straight-line segments, not curved segments.

Procedure:


1. Click on the Divide Segment icon, or select "Divide Segment" from the **Point** menu. The command name DIVIDE SEGMENT will appear in **green** on the right side of the status bar. The prompt on the command line says **Segment to divide:**
2. Click **LM** on the segment you want to divide. The segment turns red when it is selected. You can only select one segment at a time, so if you select a second segment, the first is unselected.



3. When you have selected the correct segment, press <ESC> or click **RM**. A dialog box opens, asking how many parts you want to create.



4. Enter a number and click the "OK" button. New vertices are added to the selected segment.



CORNER VERTEX command

The CORNER VERTEX command converts an arc control point of a polygon object to an ordinary (line) point. This changes the curved segment to two line segments joined by a common corner.

Procedure:

1. Select "Corner Vertex" from the **Point** menu. The prompt on the command line says **Select arc corner point to straighten:**
2. Use <F5> [SHOW VERTEX](#)¹³⁶ to turn on the points. The arc control points appear in **blue**.
3. Click **LM** on an arc control point. The point will turn **red** when it is selected.
4. **To stop selecting points**, press <ESC> or click **RM**. The point(s) you selected will be converted from a curve to a corner.

The CORNER VERTEX command may be reversed with the [ROUND VERTEX command](#)¹³³.

ROUND VERTEX command

The ROUND VERTEX command converts a Line vertex of a polygon object to an arc corner point. This changes the corner to a curve. ROUND VERTEX will not convert a vertex if the resulting object would be illegal. For instance, an object can't have two adjacent arc control points.

If you want to convert a single straight line segment into a curve, add a point first. You need three points for a curve.

Procedure:

1. Select "Round Vertex" from the **Point** menu. The prompt on the command line says **Select corner to convert to curve:**
2. Use <F5> [SHOW VERTEX](#)¹³⁶ to turn on the points. The corner points appear in **green**.
3. Click **LM** on a corner point. The point will turn **red** when it is selected.
4. **To stop selecting points**, press <ESC> or click **RM**. The corner point(s) you selected will be converted to arc control (round) points.

The ROUND VERTEX command may be reversed with the [CORNER VERTEX command](#)¹³³, which converts individual corner points back to Line points.

See also:

[ADD VERTEX command](#)^[129]

ALIGN-X command

The ALIGN-X command sets the X coordinates of two or more points to the same value. This puts the points on a single vertical line. Use this to line up points, or to tidy up vertical lines. ALIGN-X works with all types of points, including text, insertion, and dimension objects.

Procedure:

1. Click on the Align-X icon, or select "Align-X" from the **Point** menu. The prompt on the command line says `Align on vertical line with what point?`
2. Click **LM** on one point that the others will be aligned with. The point turns **red** as it is selected. You can only select one point at a time, so if you click on a second, it replaces the first.
3. **When you have the correct point selected**, press <ESC> or click **RM**. The prompt on the command line says `Select points to align:`
4. Click **LM** on one or more additional points. You can select as many points as you want by repetitive clicking.
5. **To stop selecting points**, press <ESC> or click **RM**. The selected points will be aligned on a vertical line with the first point.

See also:

[ALIGN-Y command](#)^[134]

[MOVE VERTEX command](#)^[130]

ALIGN-Y command

The ALIGN-Y command sets the Y coordinates of two or more points to the same value. This puts the points on a single horizontal line. Use this to line up points, or to tidy up horizontal lines. ALIGN-Y works with all types of points, including text, insertion, and dimension objects.

Procedure:

1. Click on the Align-Y icon, or select "Align-Y" from the **Point** menu. The prompt on the command line says `Align on horizontal line with what point?`
2. Click **LM** on one point that the others will be aligned with. The point turns **red** as it is selected. You can only select one point at a time, so if you click on a second, it replaces the first.
3. **When you have the correct point selected**, press <ESC> or click **RM**. The prompt on the command line says `Select points to align:`
4. Click **LM** on one or more additional points. You can select as many points as you want by repetitive clicking.
5. **To stop selecting points**, press <ESC> or click **RM**. The selected points will be aligned on a horizontal line with the first point.

See also:

[ALIGN-X command](#)^[134]

[MOVE VERTEX command](#)^[130]

6.5 View Menu Commands

The **View** menu contains all the commands that have to do with what you see in your drawing, and how you see things.

Many elements of the PatternMaker environment can be turned off and on as needed. These elements are described below.

The particular menu items you see will depend on which version of PatternMaker you are using. Not all commands are available in all versions.

TOGGLE GRID command

This command turns the alignment grid on and off.

Procedure:

- Select "Grid" from the **View** menu. A check mark appears in front of the menu item if the grid is turned on.
- You can also use the shortcut key <F4> for this command.
- To change the grid spacing, use the [GRID command](#)^[76] on the **Settings** menu.

See also:

[Screen objects: Alignment grid](#)^[17]
[SNAP TO GRID](#)^[140]

TOGGLE PAGE GRID command

This command shows or hides the page layout grid.

Procedure:

- Select "Page Grid" from the **View** menu. A check mark appears in front of the menu item if the page grid is turned on.
- You can also use the shortcut key <F12> for this command.

The size of this grid is determined by the size of the paper you are using in your printer. It displays the actual printable area, not the paper size. A change of printer or a different paper size will affect the appearance of the page grid.

See also:

[Page layout grid](#)^[55]
[PRINT command](#)^[109]

TOGGLE YARDAGE GRID command

This command shows or hides the yardage grid.

Procedure:

- Select "Yardage Grid" from the **View** menu. A check mark appears in front of the menu

item if the page grid is turned on.

- You can also use the shortcut key <CTRL>+<F12> for this command.


The size of this grid is determined by the "Bolt Width" setting on the Configure form. Each red-outlined panel represents one "width" of fabric (whatever you have designated that to be).

See also:

[Arrange pattern layout](#)^[52]
[Define fabric width](#)^[52]

SHOW VERTEX command

This command shows or hides all the vertices (points) in the drawing. Points are represented by an "X." Corner points are shown in **green**, and regular straight-line points are shown in **blue/cyan**.




If there are two points at the same location the Xs cancel each other out, and no "X" appears at that location.

Procedure:

- Select "Points" from the **View** menu. A submenu opens. A check mark appears in front of the menu item "Show Vertex" if the points are turned on.
- You can also use the shortcut key <F5> for this command.

SHOW NAME command

This command shows or hides the point names in the drawing. Named points are used in the grading process, and also in some of the integrated editing operations with MacroGenerator.



Procedure:

- Select "Points" from the **View** menu. A submenu opens. A check mark appears in front of the menu item "Show Name" if the point names are turned on. If you turn on the names and nothing appears, it means that no points have been named.

Note: The size of the text for point names is determined by the [DIM settings](#)^[92].

See also:

NAME POINT command

ZOOM commands

PAN commands

PAN changes your point of view in a drawing, moving the center of the drawing to a new point without changing the scale. You can use either the icons or the arrow keys to pan up/down/left/right.

The arrow keys work just like the arrows on a window scroll bar: the up arrow scrolls up in the drawing; the right arrow scrolls to the right in the drawing, etc.

You can use the <F9> key to pan so that the mouse location is at the center of the screen. With a digitizer (Grading and Marker Studio only), this works even if the digitizer cursor is off the screen.

All of the pan keys and icons can be used at any time, even if you are in the middle of another command.

See also:

[ZOOM command](#)^[137]

ZOOM commands

The ZOOM commands change the scale of your drawing on screen. PatternMaker lets you view your drawing at virtually any scale, and ZOOM has many options to select the scale you want.

Using the ZOOM commands will not change the actual size of your drawing, which is the size it prints out on paper.

Quick Zoom:

To see the entire drawing, press the <END> key. To zoom in quickly, press the <F2> key. To zoom out, press <F1>. To zoom to a specific point, put the mouse cursor on the point you want to see and press the <F3> key.

Zoom menu commands:

Procedure: Activate the ZOOM command by clicking the Zoom icon, or select "Zoom" from the **View** menu. Then, follow any of the following options:

scale:

Type **F**. You will be prompted for a number and the scale will be set to that value. The larger the number, the larger objects will appear on your screen:

- 3 makes all objects appear three times larger than before
- .25 makes all objects appear 1/4 their previous size



window:

This option draws a rectangle. Click on a point at one corner of the area you want to view (ie. upper left). Next, click on the opposite corner of the area you want to view (ie. lower right). The scale will be set so that this window fills the screen. This is the default option.



all:

Type **A**. The scale will be set so that all objects in the drawing are in view. (Objects on layers that are turned off are not considered). This has the same effect as pressing the <END> key.

previous:

Type **P**. Resets the scale to its last value.

The ZOOM options can be selected with [icons](#)^[16] or [hot keys](#)^[28]. All the icons and hot keys can be used at any time, even when you are in the middle of another command.

These Hot Key assignments can be changed on the *Hot Keys* tab of the "Configure" form, found on the **Settings** menu.

See also:

[ZOOM IN/OUT command](#)^[138]

[ZOOM ALL command](#)^[139]

[PAN command](#)^[137]

[Configure options](#)^[82]

ZOOM IN/OUT commands



ZOOM IN

Zoom in by a factor of two. This means all objects are shown twice as big as before.



ZOOM OUT

Zoom out by a factor of two. This means the drawing area contains twice as big an area as before.

See also:

[ZOOM command](#)^[137]
[ZOOM ALL command](#)^[139]
[PAN command](#)^[137]

ZOOM ALL command

ZOOM ALL zooms in or out so all objects in the current drawing are visible.

Procedure:

- Select ZOOM ALL from the **View/Zoom** menu, or press the <END> key.
- The scale will be changed and the picture redrawn so that all objects in the drawing can be seen.

Note: Any objects on layers that are turned "off" will be invisible, and they will be ignored in calculating the extent of the drawing.

See also:

[ZOOM command](#)^[137]
[ZOOM IN/OUT command](#)^[138]
[PAN command](#)^[137]

REFRESH command

The REFRESH command redraws the entire PatternMaker screen area. Occasionally Windows leaves stray marks in the PatternMaker window. Use this function to clear these up.

Procedure:

- Select "Refresh" from the **View** menu.

TO FRONT command

The TO FRONT command moves one or more objects to the front of the drawing. This is used when you need to select a vertex that is "under" or "behind" another object.

Procedure:

1. Select "To Front" from the **View** menu.
2. Click **LM** on one or more objects. You can select and unselect as many objects as you want by repetitive clicking.
3. **To stop selecting objects**, press <ESC> or click **RM**. The object(s) you selected will be moved to the front of the drawing.

See also:

[TO BACK command](#)^[140]

TO BACK command

The TO BACK command moves one or more objects to the back of the drawing. This is used when you need to select a vertex that is "under" or "behind" another object.

Procedure:

1. Select "To Back" from the **View** menu.
2. Click **LM** on one or more objects. You can select and unselect as many objects as you want by repetitive clicking.
3. **To stop selecting objects**, press <ESC> or click **RM**. The object(s) you selected will be moved to the back of the drawing.

See also:

[TO FRONT command](#)¹³⁹

6.6 Settings Menu Commands

The **Settings** menu contains commands that control all aspects of how the program looks and behaves, as well as users' measurement table information.

SNAP commands

The SNAP command sets the snap mode. When Snap is on, an "X" will follow the mouse and show the nearest snap point.

Snap is used in combination with LINE, POLY, MOVE and other drawing and editing commands. Whenever you click the mouse and there is a snap point near it, that point is selected instead of the actual mouse location. This lets you make more precise inputs.

Procedure:

- You can set the snap mode at any time with the Function (hot) keys or icons, even when you're in the middle of a command.
- If you select the "Snap" command from the **Settings** menu, you are presented with the following choices:

Option	What it does	Hot key (hold <CTRL> key down)
<i>none</i>	Turn off Snap	<CTRL>+<F1>
<i>grid</i>	Snap to grid points	<CTRL>+<F2>
<i>end</i>	Snap to endpoints or vertices	<CTRL>+<F3>
<i>nearest</i>	Snap to nearest point on object	<CTRL>+<F4>
<i>ortho</i>	Draw vertical or horizontal only	<CTRL>+<F5>
<i>midpoint</i>	Snap to midpoints of lines	<CTRL>+<F6>
<i>intersection</i>	Snap to intersection of lines	<CTRL>+<F7>
<i>offset</i>	Snap to offset from line	<CTRL>+<F8>
<i>measured distance</i>	Measure along an object from a point	<CTRL>+<F9>

The Snap mode you choose stays in effect until you make a different selection.

See also:


[Hot key functions](#)  28

LAYER command

The LAYER command is used to modify the layer list. Every object is on a layer, and only objects on layers that are turned ON can be seen. A drawing can have up to 24 layers.

Procedure:

1. Activate the LAYER command by using the hotkey <F11>, or select "Layer" from the **Settings** menu. A window appears listing information for all layers.
2. The window contains the following information:



Layer lock: Indicated with an asterisk. Objects on a locked layer remain visible, but cannot be selected.

Current layer: Indicated with an asterisk. All new objects are drawn on the current layer. Click the mouse by a different layer to switch to that layer.

Layer name: Click on the name, then type in a new name for the layer. By default, layers are named "Layer0," "Layer1," etc.

Layer color: Click on the color swatch, then select a new default color for the layer. These settings apply only to the current drawing.


Layer on/off: Click on the word "on" or "off" to turn layers on and off. Turning a layer off makes any object on that layer invisible.

Cut Ratio: (Marker Studio only) Type a number in the appropriate box, or use **LM** to increase the number, and **RM** to decrease it. (See CUT RATIO)

Reset: Set all layers back to their original colors and names.

3. Click on any item with the mouse to change or set it. When finished, click the "OK" button.
4. After the dialog box closes, the drawing will be updated to reflect the new settings.

You can also switch to a different layer by clicking the "Layer" drop-down box in the status bar



See also:

[Using Layers](#) ⁹⁸

CHANGE OBJECT command

[COLOR command](#) ⁸³

Registering PatternMaker

PatternMaker uses a serial number and unlock code system to restrict and unlock the features of the different versions (read about the [different versions](#) ⁵⁴).

When you load the program, it will be run as the Basic Viewer. The Basic Viewer will run and print the pre-designed patterns, but it does not have any drawing or editing features. You can register for a free 30-day demo, or you can purchase one of the higher versions which will give you access to more features. (Visit our web site www.patternmaker.com for current pricing information.)

Procedure:

1. Select "Register" from the **Settings** menu. The Registration form opens.
2. Enter your name and the serial number of your program, and click the "Store data" button.

A screenshot of the 'Register PatternMaker' dialog box. It is divided into three steps. Step 1: 'Enter customer name:' with the text 'Sally Stitcher' and 'Enter serial number:' with the text 'PM041201TS'. Step 2: 'Click to store customer data:' with a 'Store data' button that has a red star icon and a mouse cursor pointing to it. Step 3: 'Option A: Register via Internet' with 'Access the web form:' and 'Click to go online' button, and 'Fill out form, then click to register:' and 'Register!' button. It also includes a note: 'If you have internet access, this process should take just a few minutes.' Below this is 'Option B: Register manually' with 'ID String:' and 'Unlock Code:' fields, and a 'Register!' button. A note says: 'If you cannot register online, contact your dealer with your ID String to receive an Unlock Code.' At the bottom is a 'Close' button.


3. An ID String will appear in the lower part of the form. To complete the registration, you need to submit that ID String to receive an Unlock Code. You can do this either online or manually.
 - a. **Online registration:**
 - Click the "Go online" button. This will open a browser window.
 - Fill out the customer information. At the bottom of the form, click the "Add"

button.

- Go back to the Registration form and click the "Register" button. You will see an acknowledgement that the program has been registered. When you click "OK," you will be returned to the drawing screen, and the registered features will be activated.

b. **Manual registration:**

- Contact your dealer and quote the ID String. *Although you are welcome to contact us by phone for this process, we encourage contact by e-mail, in order to reduce the chance of error. Simply cut and paste the ID String from the Registration form into your e-mail message.*
- Your dealer will give you a password, or "unlock code." Enter this code in the field called **Unlock Code**, then click the "Register" button. You will see an acknowledgement that the program has been registered. When you click "OK," you will be returned to the drawing screen, and the registered features will be activated.




The image shows the 'Register PatternMaker' dialog box. It is divided into three steps. Step 1: 'Enter customer name:' with the text 'Sally Sticher' and 'Enter serial number:' with the text 'PM041201TS'. Step 2: 'Click to store customer data:' with a 'Store data' button. Step 3: 'Option A: Register via Internet' with buttons 'Click to go online' and 'Register!'. Below this is 'Option B: Register manually' with fields for 'ID String:' (98BAD202A5C8862A) and 'Unlock Code:' (5C88828BAD202A5C), and a 'Register!' button. A red oval highlights the 'ID String', 'Unlock Code', and 'Register!' fields. A mouse cursor points to the 'Register!' button. A note on the right says: 'If you cannot register online, contact your dealer with your ID String to receive an Unlock Code.' A 'Close' button is at the bottom.

CREATE MEASUREMENT TABLE command

Use this command to save a personal table of measurements for each user.


Procedure:

1. Select "Create Measurements" from the **Settings** menu. A dialog box opens, showing the Master Measurement Table(s) (.MMT files) that are provided by the macro designer. This is a "template" file that shows which body measurements are required by that person's designs. Each designer will provide his/her own MMT file, and they are not interchangeable.
2. Select the Master Measurement Table for the designer whose macro you are using and click the "Open" button.




3. Replace the default numbers with your own measurements. This information is taken

from your *measurement chart* (included with each macro collection). Remember to use decimal numbers, so 8-3/4 inches is 8.75 inches, and so forth. (See the Fraction Conversion Table.)



- Click the "OK" button. The **Measurements** LaunchPad window opens. Give your new measurement file a name and, if you wish, some comments.



- Note that the personal measurement tables that you create have an **.MTB** file extension. You will never accidentally overwrite the original Master Measurement Table (.MMT).

See also:


[EDIT MEASUREMENT TABLE command](#) ¹⁴⁵
[COPY MEASUREMENT TABLE command](#) ¹⁴⁶

EDIT MEASUREMENT TABLE command


This command is used to make changes to a personal measurement table that has been created.

Procedure:

- Select "Edit Measurements" from the **Settings** menu. A dialog box opens, showing the personal measurement tables (**.MTB** files) that have been created.



2. Highlight the table you want to edit, and click the "Open" button.



3. Make the necessary changes and click the "OK" button. The file is automatically saved, and you will be returned to the drawing screen.

See also:

[CREATE MEASUREMENT TABLE command](#)^[144]


[COPY MEASUREMENT TABLE command](#)^[146]

COPY MEASUREMENT TABLE command

This command is used to make a copy of a personal measurement table that has been created.

Procedure:

1. Select "Edit Measurements" from the **Settings** menu. A dialog box opens, showing the personal measurement tables (.MTB files) that have been created.



2. Highlight the table you want to copy, and click the "Open" button.
3. The measurement table opens. Make any necessary changes and then click the "OK" button.
4. Save the table with a new name.

This process is exactly the same as EDIT MEASUREMENT TABLE, except that this command gives you a chance to rename the file.

See also:

[CREATE MEASUREMENT TABLE command](#)^[144]
[EDIT MEASUREMENT TABLE command](#)^[145]

Configure/Configure Defaults


There are two ways to configure PatternMaker:

1. You can set drawing properties, viewing options, and program behaviors that will be in effect until you close PatternMaker (*Configure*); or,
2. You can choose settings that will be in effect every time you start PatternMaker (*Configure Defaults*).

When you open these two forms, they may display different information. The *Configure Defaults* form shows how PatternMaker will start up every time you open the program; the *Configure* form will display the current settings, reflecting any changes you may have made in the current session.

Configure Program Options: Program Settings

From this screen you can change many things having to do with the way PatternMaker looks and acts.



- [Draw Settings](#)^[82] Determine the appearance of objects
- [Start Folders](#)^[94] Set where LaunchPad opens
- [Grid Settings](#)^[76] Toggle grid on/off and change grid spacing
- [Undo History](#)^[97] Change number of steps you can Undo
- [File History](#)^[97] Change number of most-recently-used files on File menu
- [Dot Width](#)^[90] Change radius of "dot" pattern markings
- [XArc Pieces](#)^[91] Change the smoothness of curves
- [Active Layer](#)^[141] Selects the active layer
- [Snap Mode](#)^[140] Selects a snap mode
- [Dim Settings](#)^[92] Change how Dimension objects are displayed
- [Meas Units](#)^[76] Select inches or centimeters as your working units
- [Fabric Width](#)^[78] Define the width of fabric you will use for your pattern layout
- Show [Page Grid](#)^[77] Turn page grid on/off
- Show [Yardage Grid](#)^[77] Turn yardage grid on/off
- Show [ID Obj Panel](#)^[81] Turn ID Object Panel on/off
- Show [Vertices](#)^[136] Turn points on/off
- Show [Start Form](#)^[94] Show Start Form when PatternMaker opens
- Use [Context Menus](#)^[78] Turn right-click context menus on/off
- [Show Shared Files](#)^[96] Show the "Shared Files" location for opening and saving files
- [Show Explorer Tree](#)^[95] Show the Tree view in the LaunchPad windows
- [Use Windows Browsers](#)^[94] Toggle LaunchPad interface
- [Offset Lines](#)^[93] Toggle Offset Lines/XArc mode for drawing curves
- [White Background](#)^[79] Toggle background color from white to black
- Show Add Arrow Form Open Arrow form directly after adding a grading arrow

See also:

[Configure: Set Background Image](#)^[149]
[Configure: Status Bar](#)^[151]
[Configure: Icon Bar](#)^[152]
 Configure: Marker Settings
[Configure: Hot Keys](#)^[153]

Configure Program Options: Background Image


With the PatternMaker Home Version or higher, you can select a bitmap file (file extension [.bmp](#)) to use as a background image in the drawing area. You can use this feature to import a scanned image of a garment or a pattern piece, select it as the background image, and then use the drawing tools to trace over the image. See Using bitmap background images for more information.

The *Background Image* tab of the Configure form controls the display of a background image. If

the image area of the form is blank, there is no background image selected.

To load an image:

1. Click the "Load" button. The "Open File" dialog box appears.
2. Navigate to the location of the bitmap file (.bmp) you want to use as the background image.
3. Double-click the file, or select the file and click the "Open" button. The bitmap image will be shown in the display box.



4. Consider whether you want to use the "stretch" option. If this box is checked, the picture will be resized to fit the drawing area, but its proportions will be distorted. If you do not want to change the proportions of the image, leave this box unchecked. (However, see note below.)
5. Click the "OK" button. The image you selected will be displayed in the upper left hand corner of the drawing area.

To remove the background image:

Go to the *Background image* tab of the Configure form and click the "Clear" button. The bitmap image will be removed.

Note:

The background bitmap is, literally, in the background. It cannot be moved, resized, zoomed, or scrolled. Therefore, if your scanned image is too large to fit into the drawing area, you will not be able to trace the entire image. One way around this problem is to use the "Stretch" option on the *Background Image* tab of the Configure form.

Using "Stretch" will result in the image being distorted; however, after you have traced it, you can use the [RESIZE command](#)^[124] to ensure that your traced objects are the proper size. Measure horizontally on your original paper pattern, then use the X-measure option of the RESIZE command to adjust the POLY object to the same dimensions. Then measure vertically on the

original pattern, and use the Y-measure option of the RESIZE command.

If your original scan fits in the drawing window without using "Stretch," the proportions will not be distorted. You can probably use the [SCALE command](#)^[123], rather than RESIZE, since it adjusts both the vertical and horizontal dimensions at the same time. (Use the X/Y-Measure option of the SCALE command.)

See also:

[Configure: Program Settings](#)^[147]


[Configure: Status Bar](#)^[151]

[Configure: Icon Bar](#)^[152]

[Configure: Marker Settings](#)

[Configure: Hot Keys](#)^[153]

Configure Program Options: Status Bar



Show Panels:

- Icon If this is checked the icon Pane is displayed
- Prompt If this is checked the prompt pane is displayed
- Status If this is checked the status pane is displayed

Status Pane Elements:

This controls which elements of the status bar pane are displayed. If an element is checked it is displayed in the status bar.

See also:

[Configure: Program Settings](#)^[147]

[Configure: Set Background Image](#)^[149]


[Configure: Icon Bar](#)^[152]

[Configure: Marker Settings](#)

[Configure: Hot Keys](#)^[153]

Configure Program Options: Icon Bar

This tab is used to control the icon bar. Icons can be added, hidden and changed. Macros can also be attached to a button. Both the command and the image associated with the icon can be modified.



Changing an image:

1. Click on the image you want to change.
2. Select the new bitmap to be displayed.
3. Click the "Okay" button.

There are 20 custom images provided with PatternMaker that you can use as you wish.

Changing a command:

1. Use the drop-down box to the left of the image to select a new command. The default command may be left blank if the version of PatternMaker you have doesn't support the command associated with the bitmap (for example, the Edit Arrow in the home version).

Adding a Macro:

1. Double click in the macro edit field which is to the right of the command field. An open file dialog will appear.
2. Select the macro file you want.

The macro you select may be a frequently-used garment macro, or it may be any other sequence of actions that a programmer or designer has saved as a macro (for example, the

macro to add buttonholes to a garment).

Removing a Macro:

Delete the file name in the macro edit field. If there is text in the macro edit box it will over ride the command associated with the icon.

Rearrange the icons:

Click the up/down arrows to reorder the buttons on the icon bar

Hiding an icon:

Uncheck the "visible" checkbox to the left of the macro Edit box

Adding an icon:

If you click on the Add button an empty icon will be added at the end of the list. A bitmap, a command or macro will need to be assigned to it. It will also need to be made visible.

Defaults:

Use the Defaults button to restore the buttons to the default settings. PatternMaker must be restarted for this command to take effect.

See also:

[Configure: Program Settings](#)^[147]

[Configure: Set Background Image](#)^[149]

[Configure: Status Bar](#)^[151]


Configure: Marker Settings

[Configure: Hot Keys](#)^[153]

Configure Program Options: Hot Keys

This feature gives you the option of reprogramming the standard Hot Key assignments. If you find the <Ctrl>+<F> combinations too awkward for using the Snap modes, feel free to change them to something more convenient!

You can also save different sets of Key assignments, in case you'd like to use different keys depending on what you're doing.



Configuring the Hot Keys:

- Scroll through the list of commands to find the one you want.
- Press the key or key combination you want to use. You can use any combination of <F> keys, arrow keys, <HOME>, <END>, <INS>, <DEL>, <CTRL>, and <SHIFT>. <ALT> combinations are not available.

The Hot Key configuration files are saved in the user settings for each profile on the computer. This means that everyone who logs on to the computer can save the Hot Keys the way they like them best. You can also move your configuration file to a different computer.

See also:

[Configure: Program Settings](#)^[147]

[Configure: Set Background Image](#)^[149]

[Configure: Status Bar](#)^[151]

[Configure: Icon Bar](#)^[152]

Configure: Marker Settings

6.7 Help Menu Commands

HELP command

Use "Search," above, to select a topic from PatternMaker's list of commands.

For Icons: click right button of mouse on icon.


Click on the [green underlined text](#) to jump from topic to topic within the Help file. Use the "Back" button to go back to a topic you have already visited.

Use "Print Topic" from the **File** menu of the Help program to print out any topic as you are viewing it.


Tips and Hints



The "Tips & Hints" feature has been added to help you make the most of your PatternMaker experience by pointing out useful things you may not be aware of.



If the "Display tip of the day" checkbox is marked, the next dialog box that opens displays the tip:



If you do not wish to view the Tip of the Day, just clear the checkbox on the Start Form. (If you have turned off the Start Form, you can display it again with an option on the Configure form.)

Calculator



Selecting this option will launch the Windows calculator. This tool can be useful as you work with your pattern, if you need to add measurements together, etc.

About box

The About box displays the copyright information for PatternMaker, and also tells you which version you are using, and the build number. If you need to request technical support, the build number can be given to PatternMaker personnel in order to determine if you have the latest version.

You can also connect to the PatternMaker web site from this box. Just click on the link and it will automatically launch your browser.

Section

A large, light gray circle containing the Roman numeral 'VII' in white. A horizontal gray line extends from the left side of the circle, passing under the word 'Section'.


VII

Appendix: Using Windows dialogs instead of LaunchPad


If you choose not to use the LaunchPad interface, the File/Open, File/Save, and File/Run Macro procedures will look very different from what is pictured in the main sections of this documentation.

7.1 Create a personal measurement table


- Have someone help you take your measurements
- Open PatternMaker
- Select "Create Measurement Table" from the **Settings** menu
- Navigate to *C:/Program Files/PatternMaker Software/PatternMaker 7/Common Files/Measure*




- Open the sample measurement file called *default_women.mmt*:



- Enter your name and replace the default numbers with your own:



- Save the new table with your name:



See also:

[Using Measurement Tables](#) ⁴⁵

7.2 MACRO command


The MACRO command runs a macro. Macros are small programs that run inside PatternMaker to create basic blocks or complete patterns.

Before you run a macro, set up a personal [measurement table](#) ¹⁵⁸

Procedure:


1. Click on the Macro icon, or click "Macro" on the **File** menu.
2. A dialog box will ask you to select a file. Each macro is a file with a name ending in ".MAC", such as LPANTS.MAC. The name of each macro file is given, along with the descriptions of the macros, in the separate instructions that accompany the macro

collection. Select the macro you want to run and click the "OK" button. It may take a few seconds for PatternMaker to load the macro.



3. You will now see a series of dialog boxes which ask questions and offer choices. The choices are different for each macro. (For instance, for the womens dress, you will be asked if you want a sleeveless dress or one with sleeves.) To continue through the macro, use your mouse to click on one of the options. If you click "Cancel" the macro will abort and you will be returned to the drawing screen.
4. After you have made your choices, it's time to enter your measurements. You can either use a saved [measurement table](#) ^[144], or you can enter the measurements manually.


Using a Measurement Table



From the "Open File" dialog box, select a measurement table and click the "Open" button. The measurements from this table will be "plugged into" the macro.

NOTE: Be sure you are using a measurement table specific to the designer whose macro you are running.

Entering Measurements Manually



The macro will prompt you to select a measurement table, but if you do not want to use one, click the "Cancel" button to close the "Open File" dialog box. The macro will then display a dialog box into which you can enter your measurements. Some macros may have two dialog boxes for measurements. Fill these in from your *measurement chart*. Remember to use decimal numbers, so 8-3/4 inches is 8.75 inches and so forth. (Use the Fraction Conversion Chart for help.) Be careful to enter the right numbers in the right spaces. When you are ready, click OK or press the <ENTER> key.

5. While the macro is running, the mouse pointer icon turns into an hourglass. You may have to wait for the macro to run, especially if you do not have a fast computer, or if the macro you are using is particularly complicated. You will know the macro is done when the hourglass cursor changes back to an arrow and the prompt Command : appears on the status bar.

IF YOU CANNOT SEE THE PATTERN PIECES, OR IF YOU ONLY SEE PART OF THEM, PRESS THE <END> KEY TO VIEW ALL THE PIECES IN THE DRAWING.

The macro will draw your new pattern in the drawing area. If there is a drawing on the screen when you run a macro, the macro will be *added to* what is on the screen. It may overlap existing pattern pieces. If this happens you can use the [MOVE command](#)^[118] to move things around. Use the [ZOOM](#)^[137] and [PAN](#)^[137] commands to view different parts of the drawing.

A macro can be run as many times as you wish. With the Deluxe Editor or higher, you can reuse your own measurement table, and you can create new tables for many different people.


Once the macro has created the pattern on the screen, the drawing can be saved as a **.PAT** file, to be opened and printed again later. With the Deluxe Editor or higher, you can also edit the .PAT file, but you cannot automatically change the body measurements used in the garment. To change the measurements, run the macro again.

7.3 Save a pattern file

The SAVE AS command saves the current drawing with a new file name, while leaving the current file unchanged. Use this to save your new work without erasing your old work.

Procedure:

1. Select "Save As" from the **File** menu. The Save File dialog box appears.
2. If necessary, navigate to the location where you want the file to be saved.
3. Type a name for your file, or select a file from the list. If the filename you select or type already exists, that file will be overwritten. If you type a new name, a new file is created.
4. PatternMaker automatically adds the ".PAT" extension. If you want to save in a different format, for example .DXF, click the "Save as Type" drop-down box, and select the file type from the list.
5. Click the "Save" button.



See also:


[SAVE command](#)^[107]
DXF Import/Export

7.4 OPEN command

The OPEN command opens an existing drawing (a .PAT file) which has been saved on disk. Opening a new file replaces whatever is on the screen. If there is a drawing open, the program will ask you if it should be saved.

Procedure:

1. Click the Open icon, or select "Open" from the **File** menu. The Open File dialog box appears.
2. If necessary, navigate to the location of the file you want to open.
3. By default, .PAT files (PatternMaker format) are displayed. If you want to open a different format, for example .DXF, click the "Files of Type" drop-down box and select the file type from the list (see picture).
4. Select the file you want to open.
5. Click the "Open" button.



You can open a PatternMaker Backup file (.BAK) through the OPEN command. This is useful if you've made a major mistake in your drawing that the [UNDO command](#)^[117] cannot fix, and you

need to go back to a previous version of your file.

See also:

DXF Import/Export

Section



VIII

Troubleshooting & Support

8.1 Frequently-asked questions

Where do the macros come from?

There are many talented and creative people around the world creating macros! The original collections were produced by a Finnish designer, Leena Lähteenmäki. She created patterns for basic, classic garments. Other designers are now producing macros for Renaissance costumes, wedding gowns, and many other applications.

PatternMaker Software publishes another program called MacroGenerator which helps designers to create the macros without requiring knowledge of computer programming. For information about MacGen, please go to [the PatternMaker website](#).

Can I create my own macros?

If you have PatternMaker Home Studio, you have a unique tool called the Macro Project Editor. This lets you create simple macros for patterns that adjust only in two dimensions -- for example, an unusual pillow design, or a pattern for a hat.

If you want to create patterns that will adjust in three dimensions -- almost any type of clothing -- you can use a program called Macro Generator, also from PatternMaker Software. [Click here](#) for more information about MacGen.

Can I adjust the body measurements after a pattern is on the screen?

No. Once the pattern is drawn, it is defined as a specific size. To change the measurements, re-run the pattern.

8.2 Identifying and solving problems

None of the drawing or editing commands work

1. Make sure you're not in the middle of some other command (check the status bar).
2. Make sure the program version you are using is supposed to offer drawing and editing commands.

I've purchased the program, but it tells me I only have XX number of days to use it

If you see this message after you've purchased the Deluxe version or higher, it means you haven't registered the program yet. Go to the "Registration" form on the **Settings** menu and follow the directions there. (See [Registering PatternMaker](#)^[142] for more details.)

I can't install a macro collection

All the macro collections require a password to install them. You receive the password when you order, either in an e-mail, if you order by download, or on the macro package if you order through the mail. After the collection is installed, be sure to write down the password, since you will need it to install future macro updates.

The lines on the printed pattern are too light

Set your printer to its *lowest* resolution. Lower resolution means fewer dots per inch; fewer dots per inch means each dot is larger. When PatternMaker prints something, it prints each line "one dot" wide. Therefore, if the printer is printing larger dots, the pattern lines are thicker/darker.

See [Configure: LINE WIDTH](#)^[88]

I can't make this command work

Every command has detailed step-by-step instructions in the Reference section of the Help file.

8.3 Getting Help

There are several avenues available to you if you need help.

1. First, check the Help file. It has been expanded to make it easier to find what you need. You can access the Help file from the **Help** menu, or by typing ? during a command to access the context-sensitive help.
2. Next, check the Index of the User's Manual, and the Index of the Tutorial. You may be able to find a reference to something you didn't notice in the Help file.
3. If it's a piece of terminology that's puzzling you, check the [Glossary](#)^[166].
4. Finally, you can contact technical support by phone or by e-mail. Also consider joining the PatternMaker User's Group e-mail discussion list. Check the PatternMaker web site for instructions on how to join:

www.patternmaker.com

You can use the link in the "About" box (located on the **Help** menu) to automatically launch your browser and go directly to our site.

5. As long as you're there, check the web site for an answer to your question. We've posted answers to many frequently asked questions, and you may find what you need in that reference.

8.4 Glossary

absolute mode

One of two modes available when using a *digitizer tablet*. In this mode, the digitizer tells the program where the cursor is. The other mode is *mouse mode*.

arc

A curved line segment. An arc has three *vertices* – one at each end, and a "control point" which acts like a magnet to control the shape of the curve.

armscye

Armhole

click

Press the left mouse button (**LM**) one time and release it.

command line

The blue area at the bottom of the PatternMaker window which displays command information.

coordinates

A system used to indicate position on a grid. The grid can measure units either in inches or in centimeters. The X coordinate counts units in a horizontal direction, and the Y coordinate counts units in a vertical direction.

digitizer (digitizer tablet)

A computer accessory used to draw or trace lines and shapes and communicate that information

to the computer. Digitizers can range from the size of a notepad to the size of a kitchen table.

dimension (Dim)

One of four types of *objects* in PatternMaker. Dimension objects are used to measure straight-line distances between points.

double-click

Press and release the left mouse button (**LM**) two times, quickly.

drop-down menu

A sub-menu that appears ("drops down") when you click on an item in the *menu bar*.

grading

After you've drafted a pattern in one size, grading is the process of defining "rules" that tell the program how to move certain points of the pattern to create larger and smaller sizes.

group

n. two or more objects which actions are performed upon as if they were one unit.

v. to select two or more objects and tell the program to consider them as one unit.

icons

Small pictures that represent commands. Click on an icon to activate the corresponding command.

insertion point

The location on a *symbol* (one of its *vertices*) where you click to select it, or where you click in the drawing to position the symbol.

interpolate

To make an estimation based on surrounding information. A grading arrow can be interpolated by using the values of the arrows on either side of it.

library

A collection of *symbols* from which you can select and insert into your drawing.

macro

A small add-on program that is run by PatternMaker to automatically draw pre-designed garments according to a user's measurements.

master measurement template (MMT)

A measurement "template" provided by the macro designer which indicates the measurements that need to be taken. A personal measurement table is created from the master measurement template file.

measurement table (MTB)

A list of a user's custom measurements. A measurement table is specific to a particular designer's macros.

menu bar

The line of words along the top of the PatternMaker window which contains all the program commands.

mouse mode

One of two modes available when using a *digitizer tablet*. In this mode, the digitizer works like an ordinary mouse. The other mode is *absolute mode*.

object

Something that you draw in PatternMaker. There are four types of Objects: Poly, Dim, Text, and Symbol.

origin (digitizers)

The position that the *coordinates* (0, 0) are measured from.

point

1) A *vertex* of an object; 2) a location in the drawing. The meaning should be clear from the context.

polar coordinates

A method of describing the location of a point using the length of a line and the direction (in degrees) in which it points.

polygon (Poly)

One of four types of *objects* in PatternMaker. Any object that is not a Symbol, Text, or a Dimension object is a Polygon object. Polygons can be open or closed, and can have any number of *vertices* (points).

scale (digitizers)

The ratio between the size of the object to be digitized and the size you want the object to be in your drawing. A scale of "4" means that 1 inch on the digitized object equals 4 inches in your drawing. In other words, this object is 1/4 size.

segment

A section of an object between two adjacent *vertices*.

status bar

The area of the PatternMaker window under the *menu bar*. This area shows the current drawing color, fill pattern, line type and other settings, and also the current mouse position and the current command.

symbol

One of four types of *objects* in PatternMaker. Symbols consist of one or more objects grouped together with a single insertion point. The single insertion point allows you to add several objects to your drawing in a single step. Symbols can include such things as grainlines, buttonholes, or copyright information.

tangent

A line that continues a segment of a *polygon* in the direction of the last segment.

text

One of four types of *objects* in PatternMaker. Text is used to insert labels on pattern pieces or add descriptive information.

vertex (vertices - pl.)

The beginning/end of a line segment, or the place where two line segments come together. For example, a triangle has three vertices, one at each corner.

Index

▪	
.BMP files	149
.DXF files	102, 106, 108
.GRD files	102
.KEY files	102
.MAC files	102, 111
.MIF files	102
.MMT files	49, 102
.MTB files	49, 51, 102, 144, 145, 146
.PAT files	102, 106, 107, 108

A

About box	156
absolute coordinates	34, 35
activating a command	26, 29
active layer	99
add text to a drawing	65
ADD VERTEX command	129
adding seam allowance	115, 116
adjust arc lengths	74
advanced features of PatternMaker	5
advanced Snap modes	103
aligning printed pages	62
alignment grid	76
set spacing	76
showing/hiding	17, 135
alignment marks and page labels	61
ALIGN-X command	134
ALIGN-Y command	134
all objects	31
selecting	31
arcs	74
adjusting length	74
drawing	71, 91
measuring	74
arrange pattern pieces	52
assembling printed pages	54, 62
attach a macro to an icon	152
automatic garments	111

B

background color	79
------------------	----

background picture	149
base point	67, 68, 72, 73
basics of PatternMaker	7
begin a new drawing	106
black background	79
bolt width	77, 78

C

calculate fabric yardage	77
calculate number of pages	135
calculator	155
canceling a command	30, 117, 118
can't find files	12
centimeters vs inches	12, 76
change background color	79
change curve to/from corner	133
change drawing color	83
change fill pattern	85
change the image on an icon button	82, 152
change the order of the icons	152
changing Hot Key assignments	82
choose LaunchPad vs Windows dialogs	94
choose pages to print	56
close PatternMaker	114
color (drawing color)	83, 101
columns vs rows	61, 62
combine drawings	107
combining styles from different macros	45
command line	14
configuring	79
commands	29
activating	29
canceling	30
repeating	30
selecting	29
typed input	26
using drop-down boxes	26
using Hot Keys	26, 28
using icons	26
using menus	26
ZOOM	25
compare programs	5
configure floating windows	81
configure Hot Keys	82, 153
configure program options	152
configure/configure defaults	147
configuring drawing preferences	82

configuring main window	76
configuring menus and dialog boxes	93, 94
configuring PatternMaker	79, 151
context menus	78
coordinate system	34
coordinates	35
absolute	35
polar	36
relative	36
using (Example)	37
COPY command	119
COPY MEAS command	146
copying measurement tables	146
corner	133
convert to/from curve	133
CORNER VERTEX command	133
counting pages	56
create a personal measurement table	49, 51
creating measurement tables	144
current layer	99
curves	74
adjusting length	74
drawing	71, 91
measuring	74
custom fit garments	40, 41, 43, 45
custom-fit garments	111
customizing icon bar	82
customizing PatternMaker	76, 79, 82, 93
CUT command	127, 128

D

default layer settings	101
layer color	101
restore	102
default program settings	147
define fabric width	52
DELETE SEGMENT command	131
DELETE VERTEX command	130
deleting objects	125
deselecting objects/points	31
destination	67, 68, 72, 73
DIM command	114
Dim settings	92
Dimension objects	66
change settings	92
DIVIDE SEGMENT command	132
do this by default	13

DOT command	90
dot width	90
dotted/dashed lines	89
drawing an object	67
drawing area	14, 24, 25
drawing color	83, 101
drawing curves	71, 91
drawing from scratch	65
drawing lines	115
drawing preferences	82, 147
drawing shapes	115
drop-down boxes	26

E

EDIT MEAS command	145
editing measurement tables	145
editing objects	67, 130, 131
editing points	72
editing the icon bar	152
entering points	70
typed coordinates	34
using snaps	32
ERASE command	125
estimate fabric yardage	51, 77
evenly-spaced vertices	132
Example: MOVE command	68
Example: MOVE VERTEX command	73
Example: Using coordinates	37
EXIT command	114
Explorer tree	22
show/hide	95

F

fabric layout grid	51, 52, 135
fabric width	52
fabric yardage	77, 78
features in Version 7	6
features of PatternMaker	5
file history	97
file icons	22
file locations	12, 18
file management	18, 19, 20, 21, 107, 108
file organization	12
file tree	22
file types	102

-
- files 106
 - begin new 106
 - combine 107
 - opening 19, 20, 106
 - printing 109
 - renaming 108
 - saving 21, 107
 - fill pattern 85
 - changing 85
 - finding files 12, 18
 - fit to page (printing) 59
 - fix a mistake 30
 - FLIP HORIZ command 126
 - FLIP VERT command 127
 - floating windows 81
 - focus pictures 18, 19, 20, 21, 22
 - font 86
 - changing 86
 - frequently-asked questions 165
 - function keys 26, 28
-
- G**
- Getting Started 11
 - glossary 166
 - GRID command 76
 - grid spacing 76
 - grids 17, 135
 - alignment grid 17, 135
 - page grid 135
 - yardage grid 51, 52, 135
-
- H**
- help 155
 - hide/show Explorer tree 95
 - hide/show layers 101
 - hide/show points 17, 136
 - hide/show shared files 96
 - hide/show Start form 94
 - highlighting objects/points 31
 - hints and tips 14, 155
 - horizontal alignment 134
 - Hot Keys 26, 28
 - configuring 82
 - how to get help 11, 166
 - how to run a macro 43
 - how to take measurements 46
 - how to use the mouse 25
-
- I**
- icon bar 14
 - customizing 82
 - editing 152
 - icon list 16
 - icons 16, 26
 - ID Object Panel 81
 - ID String (registering PatternMaker) 142
 - identify objects and points 81
 - inches vs cm 12, 76
 - interacting with the program 24
-
- J**
- JOIN command 128
-
- L**
- labels 65
 - adding to a drawing 65
 - landscape vs portrait 59, 111
 - LaunchPad interface 18
 - opening files 19, 20, 106
 - options 22
 - saving files 21, 107
 - LAYER command 99, 141
 - layers 98
 - configuring 141
 - default colors 101
 - locking 102
 - naming 100
 - reset defaults 102
 - select active 99
 - showing/hiding 101
 - laying out a pattern 52
 - learning the program 11
 - length of file history 97
 - length of Undo history 97
 - library files 102
 - LINE command 115
 - line segments 74
 - adjusting length 74
 - deleting 131
 - line styles 88, 89
 - line width 88
 - LM 7, 25

location of files	12
lock a layer	102
looking around the drawing	24, 25, 137, 138, 139

M

MACRO command	111
macros	40, 41, 43, 44, 45
using	19, 20
main drawing window	76
MEAS command	144
measure between two points	114
measurement pictures	44
measurement tables	51
changing	51
copying	146
creating	49, 144
editing	145
using	45, 46, 111
using in a macro	49
measurement units	12
choosing	76
measurements	146
copying measurement tables	146
creating measurement tables	144
editing measurement tables	145
how to take	46
measuring between points	66
menu bar	14
menus	26
right-click	78
MERGE command	107
MIRROR command	119
mouse actions	25
mouse scrolling	25
mouse snaps	32, 103, 140
MOVE command	68, 118
move the command line	79
MOVE VERTEX command	73, 130
moving objects to front or back	139, 140
moving points/objects	72
multiple undo/redo	30, 117, 118

N

name a layer	100
narrow/wide lines	88
NEW command	106

new features in Version 7	6
number of pages	135
number of Undos	97

O

objects	102
assigning to layers	102
changing size or shape	123, 124
copying	119
cutting	127
Dimension	66
drawing	67
editing	67
erasing	125
identifying	81
joining	128
moving	118
moving to front or back	139, 140
reversing/reflecting	119, 121, 126, 127
rotating	122
selecting	30, 31, 32, 33
Text	65
types of	65
unselecting	31
working with	65, 67
OFFSET command	115
offset lines	93
old-style dialog boxes	93, 94
open a file	106
open a macro	19, 20
open a pattern	20
open a pre-designed garment	19, 20
open a saved pattern	20
OPEN command	106
open files	94
open multiple files	107
options for selecting objects/points	31
options in LaunchPad interface	22
orientation of pages	59
overview of points	70

P

page grid	55
show/hide	77, 135
page labels and alignment marks	61
page orientation	59, 111

-
- page rows/columns 62
 - PAN commands 24, 137
 - parts of the screen 14, 16
 - pattern (fill pattern) 85
 - pattern layout 52
 - pattern markings 90, 114, 115, 116
 - PatternMaker 142
 - registering 142
 - PatternMaker basics 7
 - patterns 62
 - assembling printed pages 62
 - custom-fit 111
 - printing 109, 135
 - personal measurement tables 51, 144, 145, 146
 - point names 137
 - show/hide 137
 - point selection window 33
 - points 129
 - adding 129
 - aligning 134
 - deleting 130
 - editing 72
 - entering using snaps 32
 - identifying 81
 - moving 130
 - rotating 131
 - selecting 30, 31, 32, 33
 - show/hide 17, 136
 - types of 70
 - unselecting 31
 - working with 70
 - polar coordinates 34, 36
 - portrait vs landscape 59, 111
 - pre-designed garments 40, 41, 43, 44, 45
 - print a selected pattern piece 110
 - print a specific page 56
 - print at 1/4 or 1/2 scale 57
 - print columns first 61
 - PRINT command 109
 - print only a portion of a drawing 111
 - Print options 61
 - print preview 56
 - PRINT REGION command 111
 - print rows first 61
 - PRINT SELECT command 110
 - print setup 59
 - PRINT SETUP command 111
 - print to a single page 59
 - printable area 55
 - printed pages 62
 - assembling 62
 - printing out a pattern 54, 55, 56, 62, 135
 - program comparison 5
 - program version number 156
 - program versions 5
 - prompt line 14
 - putting a pattern together 54
-
- Q**
- quit 114
-
- R**
- reaching technical support 11, 166
 - rearrange the icons 152
 - recently-used files 97
 - redo a command 30
 - REDO command 118
 - reflect an object 119, 121, 126, 127
 - REFLECT command 121
 - REFRESH command 139
 - REGISTER command 142
 - relative polar coordinates 36
 - relative X/Y coordinates 34, 36
 - remove a line segment 131
 - removing a point 130
 - rename a file 108
 - reorder the icons 152
 - repeating a command 30
 - reset layer settings to default 102
 - RESIZE command 124
 - restore default layer settings 102
 - reverse an object 119, 121, 126, 127
 - right-click context menus 78
 - RM 7, 25
 - ROTATE command 122
 - ROTATE VERTEX command 131
 - ROUND VERTEX command 133
 - rows vs columns 61, 62
 - rules of using the mouse 25
 - running a macro 111
-
- S**
- save a file 21
 - SAVE AS command 108

SAVE command	107	show/hide yardage grid	52, 77, 135
scale a pattern to print	57	shrink drawing to one page	59
SCALE command	123	size	123, 124
scanned pattern	149	changing	123, 124
importing to PatternMaker	149	SNAP commands	140
screen	14, 16	Snap modes	32, 103
parts of	14, 16	Snap To Endpoint	30
scroll with the mouse	25	special selection tips	32
seam allowance	115	Start form	13
fixed-width	115	show/hide	94
variable-width	116	Start locations	94
SEAM ALLOWANCE command	116	starting PatternMaker	8, 13
segment (line)	74	status bar	14, 151
adjusting length	74	style option pictures	43
deleting	131		
select a command	29		
select active layer	99	T	
select pages to print	56	taking measurements	46
selecting a command	26	tape pages together	62
selecting all objects	31	technical support	11, 166
selecting objects	30, 31, 32, 33	terminology	11, 166
selecting points	30, 31, 32, 33	Text objects	65
selection window	31	Tip of the Day	14
set current drawing properties	85, 86, 88, 89, 92	tips and hints	155
set drawing preferences	82	TO BACK command	140
set file history	97	TO FRONT command	139
set grid spacing	76	TOGGLE GRID command	17, 135
set preferences	147	TOGGLE PAGE GRID command	135
set Start locations	94	trace a scanned pattern	149
set Undo history	97	troubleshooting	165
setting measurement units	12, 76	turn grids on/off	17, 52, 135
shapes	115	turn layer on/off	101
drawing	115	typed commands	26
shared files	96	typed coordinates	34
show/hide	96	typeface	86
shortcut keys	26, 28	changing	86
view page grid	55	types of files	102
SHOW NAME command	137	types of objects	65, 66
SHOW VERTEX command	17, 136	types of points	70
show/hide alignment grid	17, 135	typing in a drawing	65
show/hide command icons	152		
show/hide Explorer tree	95	U	
show/hide ID Object Panel	81	undo a command	30
show/hide layers	101	UNDO command	97, 117
show/hide Page Grid	77, 135	undo history	97
show/hide points	17, 136	UNITS command	76
show/hide shared files	96	Unlock Code (registering PatternMaker)	142
show/hide Start form	94		

unselecting objects/points	31
use a measurement table in a macro	49
using a macro	19, 20
using a mouse	25
using layers	98
using macros	111
using measurement tables	45, 46, 111
using scanned images	149
using Snap modes	32
using the pre-designed garments,	41, 43, 44, 45

V

version	156
Version 7 features	6
versions of PatternMaker	5
vertical alignment	134
vertices	129
adding	129
aligning	134
deleting	130
editing	72
moving	130
rotating	131
show/hide	17, 136
types of	70
view Explorer tree	22
view options (LaunchPad)	22
viewing a drawing	137, 138, 139, 140

W

what is a macro?	40, 41, 43
where files are stored	12
white background	79
wide/narrow lines	88
window selection (objects/points)	31
window style	93
Windows basics	7
working with files	18, 19, 20, 21, 106, 107, 108
working with objects	65, 67
working with points	70

X

X- and Y-coordinates	34
Xarcs	71, 91

Y

yardage estimation	52, 77
Yardage Grid	77
show/hide	77
showing/hiding	52, 135
YARDAGE GRID command	51, 135

Z

ZOOM ALL command	139
ZOOM commands	24, 25, 137
ZOOM IN/OUT commands	138